TeliViewer

User manual

Version 1.0.4 (2024/06/20)

Toshiba Teli Corporation

Information contained in this document is subject to change without prior notice.

Index

1. Introduction	
1.1. Terms	
2. System Configuration	
3. Operation Environment	6
3.1. Regarding Streaming of Multiple Cameras	6
4. Installation	
5. Launch of TeliViewer	
5.1. Windows	
5.1.1. Launch from Start menu	/
5.1.2. Laurich hom Search result	
5.2.1. Launch from Search result	
5.2.2. Launch from filer or terminal	
6. Structure of TeliViewer	
7. TeliViewer features	
7.1. Discovery	
7.1.1. Updating Camera List	
7.1.2. Camera Open/Close	
7.1.3. Camera List	
7.1.4. Open camera with external XML file	
7.1.5. Features for GigE camera	11
7.1.5.1. Access mode selection	12
7.1.5.2. Launch "IP Configuration tool"	
7.2. Main window	
7.2.1. Control for stream	
7.2.1.1. Start	
7.2.1.2. Pause	
7.2.1.3. Stop	
7.2.2. Scroll feature	
7.2.2.1. Drag mode	
7.2.2.2. Auto mode	
7.2.3. Zoom feature	
7.2.3.1. Using the slider	
7.2.3.2. Fit mode	
7.2.3.3. Actual size (100%)	
7.2.3.4. Using the spin box	15
7.2.3.5. Using the Ctrikey + mouse wheel	
7.2.4.1 Dialog for save	
7.2.4.2. Save the lines on image	
7.2.4.3. Setting for save	
7.2.4.4. Folder	
7.2.4.5. Filename	
7.2.4.6. File format	
7.2.4.7. Header of RAW format	
7.2.4.8. Save button	
7.2.5. Loupe	
7.2.5.1. Launch of Loupe	
7.2.6. Draw lines on image	
7.2.6.1. Grid	
7.2.6.2. 4x4	20
7.2.6.3. Move 4x4 by mouse drag	21
7.2.7. Tab control	22
7.2.7.1. Change current camera	22
7.2.7.2. Tab detachment	
7.2.8. Multi display	
7.2.8.1. 2in1	
7.2.8.2. 4in1	
7.2.9. Full Screen display	
7.2.9.1. Start Full Screen	
7.2.9.2. End Full Screen	25

			e Settings	
	7.2.1	0.1.	Bayer convert option	26
			Interpolation display method	
			Set maximum display rate	
			Image display mode	
			Image processing	
7.3.	. Fe	ature	View	28
7	.3.1.	ToolE	Bar	28
	7.3.1	1.1.	Reload	28
	7.3.1	1.2.	Format Selection	29
	7.3.1	1.3.	Filter Selection	29
	7.3.1	1.4.	Enable FavoritesList	29
	7.3.1	1.5.	Save/Load camera features	29
	7.3.1	1.6.	Save XML to file	32
	7.3.1		Access module selection	
	7.3.1	1.8.	GenlCam cache setting	32
	7.3.1	1.9.	String search	32
	7.3.1	1.10.	Delete button for string search	33
7			uresList	
	7.3.2		Color of feature in list	
	7.3.2		How to change the value	
7			ritesList	
	7.3.3		Add feature	
	7.3.3		Remove feature	
	7.3.3		Remove all features	
	7.3.3		Sort features	
	7.3.3		How to change the value	
7			cription pane	
7.4.			og	
			r Event list	
			it filter selection	
			ils of Event list	
			e events	
7.5.			event	
			r camera events	
7	.J. 1. 5.2	Turn	ON/OFF camera event	38 31
7	.J.Z.	Solo	ct camera event	20
7	.5.5. E 1	Sove	e camera events in list	50
				20
		Ontic		
7.6.	.ט.ט.		on settings	39
/ n	0	Cam	on settingsera evet list	39 40
		Cam amera	on settings era evet list . Control panes	39 40 40
7	.6.1.	Cama amera Type	on settingsera evet list	39 40 40 40
7	.6.1. .6.2.	Cama amera Type Displ	on settings era evet list Control panes of panes lay the details of feature	39 40 40 40 41
7 7 7	.6.1. .6.2. .6.3.	Camera Type Displ Displ	on settings era evet list Control panes of panes lay the details of feature lay the settable value range	39 40 40 40 41 41
7 7 7	.6.1. .6.2. .6.3. .6.4.	Camera Type Displ Displ Utiliz	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons	39 40 40 40 41 41
7 7 7	.6.1. .6.2. .6.3. .6.4. 7.6.4	Camera Type Displ Displ Utiliz	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button	39 40 40 41 41 41
7 7 7 7	.6.1. .6.2. .6.3. .6.4. 7.6.4	Camera Type Displ Displ Utiliz 1.1.	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button	39 40 40 41 41 41 42
7 7 7 7	.6.1. .6.2. .6.3. .6.4. 7.6.4 7.6.4	Camera Type Displ Displ Utiliz 1.1. Rega	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features	39 40 40 41 41 41 42 42
7 7 7 7 7	.6.1. .6.2. .6.3. .6.4. 7.6.4 7.6.4 .6.5.	Camera Type Displ Displ Utiliz 1.1. Rega Reco	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage	39 40 40 41 41 41 42 42 43
7 7 7 7 7 7.7.	.6.1. .6.2. .6.3. .6.4. 7.6.4 7.6.4 .6.5. .6.6.	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Recoulticas	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage	39 40 40 41 41 41 42 42 43 44
7 7 7 7 7 7.7.	.6.1. .6.2. .6.3. .6.4. 7.6.4 7.6.4 .6.5. .6.6. Mu	Camera amera Type Displ Utiliz 1.1. Rega Reco ulticas Over	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage	39 40 40 41 41 41 42 43 44 44
7 7 7 7 7 7.7.	.6.1. .6.2. .6.3. .6.4. 7.6.4 7.6.4 .6.5. .6.6. Mu .7.1.	Camera amera Type Displ Displ Utiliz 1.1. Rega Reco ulticas Over Acce	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view less Mode Setting	39 40 40 41 41 41 42 43 44 44 45
7 7 7 7 7 7.7. 7	.6.1. .6.2. .6.3. .6.4. .7.6.4 .6.5. .6.6. .7.1. .7.2.	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco Ulticas Over Acce Multi	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting	39 40 40 41 41 41 42 42 43 44 45 45
7 7 7 7 7 7.7. 7	.6.1. .6.2. .6.3. .6.4. .7.6.4 .6.5. .6.6. .7.1. .7.2. .7.3. .7.4.	Camera Amera Type Displ Utiliz 1.1. 1.2. Rega Recoulticas Over Acce Multi- Deta	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting ils for Setup	39 40 40 41 41 42 43 44 45 46
7 7 7 7 7 7.7. 7	6.1. 6.2. 6.3. 6.4. 7.6.4 7.6.4 6.5. 6.6. Mt. 7.1. 7.2. 7.3. 7.4.	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1.	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting ils for Setup Determine MaxPacketSize	39 40 40 41 41 41 42 43 44 45 46 46
7 7 7 7 7 7.7. 7	6.1. 6.2. 6.3. 6.4. 7.6.4 7.6.4 6.5. 6.6. Mu 7.1. 7.2. 7.3. 7.4. 7.7.4	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1. 1.2.	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting ils for Setup Determine MaxPacketSize Setup for Controller	39 40 40 41 41 42 43 44 45 46 47
7 7 7 7 7 7 7.7. 7	6.1. 6.2. 6.3. 6.4. 7.6.4 6.5. 6.6. Mu 7.1. 7.2. 7.3. 7.7.4 7.7.4 7.7.4	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1. 1.2. 1.3.	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting ils for Setup Determine MaxPacketSize Setup for Controller Setup for Listener	39 40 40 41 41 41 42 43 44 44 45 46 47 47
7 7 7 7 7 7 7.7. 7 7	6.1. 6.2. 6.3. 6.4. 7.6.4 6.5. 6.6. Mu 7.1. 7.2. 7.3. 7.7.4 7.7.4 W	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1. 1.2. 1.3. avefor	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view less Mode Setting cast Setting ils for Setup Determine MaxPacketSize Setup for Controller Setup for Listener	39 40 40 41 41 41 42 43 44 44 45 46 47 48
7 7 7 7 7 7.7. 7 7 7 7	6.1. 6.2. 6.3. 6.4. 7.6.4 6.5. 6.6. Mu 7.1. 7.2. 7.3. 7.7.4 7.7.4 Ve	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1. 1.2. 1.3. avefore	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view less Mode Setting cast Setting ils for Setup Determine MaxPacketSize Setup for Controller Setup for Listener Imperior Setup Imperior Setup Imperior Setup Setup Setup Setup for Listener Imperior Setup Setup Setup Setup Setup Setup for Listener Imperior Setup Setup Setup Setup Setup Setup for Listener Imperior Setup S	39 40 40 41 41 41 42 43 44 44 45 46 47 48 49
7 7 7 7 7 7 7 7 7 7 7 7 7.8. 7.9.	6.1. 6.2. 6.3. 6.4. 7.6.4 7.6.4 6.5. 6.6. 7.1. 7.2. 7.3. 7.7.4 7.7.4 Ve	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1. 1.2. 1.3. avefor ectorse stogra	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting ils for Setup Determine MaxPacketSize Setup for Controller Setup for Listener rm cope	39 40 41 41 41 42 43 44 44 45 46 47 49 50
7 7 7 7 7 7.7. 7 7 7 7 7.8. 7.9. 7.10	6.1. 6.2. 6.3. 6.4. 7.6.4 7.6.4 6.5. 6.6. 7.1. 7.2. 7.7.4 7.7.4 Ve 0. Hi	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi 1.2. 1.3. avefor ectorse stogra	on settings era evet list Control panes of panes lay the details of feature ay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ont set wiew less Mode Setting cast Setting lis for Setup Determine MaxPacketSize Setup for Controller Setup for Controller Setup for Listener Import of Setup	39 40 41 41 41 42 43 44 44 45 46 47 47 48 50 51
7 7 7 7 7 7.7. 7 7 7 7.8. 7.9. 7.10 7.11	.6.16.26.36.4. 7.6.4 7.6.4 .6.56.67.17.27.37.4 Ve 0. His	Camera Type Displ Displ Utiliz 1.1. 1.2. Rega Reco ulticas Over Acce Multi Deta 1.1. 1.2. 1.3. avefore ectorse stogra ave/Lo deo re	on settings era evet list Control panes of panes lay the details of feature lay the settable value range ing the Update Buttons Update button Auto Update button arding grayed out features ommended usage st view ess Mode Setting cast Setting ils for Setup Determine MaxPacketSize Setup for Controller Setup for Listener rm cope	39 40 41 41 41 42 43 44 44 45 46 47 47 48 51 51

7.12.2. Installation of GStreamer	
7.12.2.1. Windows	
7.12.2.2. Linux based OS	54
7.12.3. Video recording settings	54
7.12.3.1. File path	55
7.12.3.2. File name	
7.12.3.3. File format	
7.12.3.4. Use encoder	
7.12.3.5. Limit Max video frame rate	
7.12.3.6. Limit Max frame to save	
7.12.3.7. Optimization for uncompressed video	56
7.12.4. Recording the video	
7.12.4.1. Start recording	
7.12.4.2. Stop recording	
7.13. Snapshot Recorder	
7.13.1. Snapshot Recorder Settings	
7.13.1.1. Folder Path	
7.13.1.2. File Name	
7.13.1.3. File Format	
7.13.1.4. Recording Mode	
7.13.1.5. Frame Count	
7.13.1.6. Repetition Cycle	
7.13.1.7. Start Image Saving	62
7.13.1.8. Stop Image Acquire (Stop Image Saving)	
7.13.1.9. Progress (Acquire, Saving)	63
7.13.2. Saving still images.	64
7.13.2.1. Start saving still images	
7.13.2.2. Stop saving still images	
7.14. Tools	67
7.14.1. Launch "IP Configuration tool"	67
7.14.2. Options	67
7.14.2.1. Updating interval of charts	
7.14.2.2. Save and restore Grid/4x4 settings	
7.14.2.3. Save and restore camera streaming status	68
7.14.2.4. Launch with full screen	
7.14.2.5. Hide exit button and cursor on full screen	60
7.14.2.5. Prokaround Color	09 60
7.14.2.6. Background Color	
7.14.2.7. 2in1/4in1 setting	09
7.14.2.8. Enable stream stats collection	
7.14.2.9. Enable GenTL devices	/ 1
7.14.2.10. Maximum messages in Status Log	
7.14.2.11. RestoreDefault	
7.15. Help	
7.15.1. Open user manual	
7.15.2. About	
8. Appendix	
8.1. Enlargement of the pane to the four corners	73
8.2. About Save/Restore settings for TeliViewer	74
8.3. U3V Camera Specific Information	
8.3.1. BERT feature	
8.3.1.1. Usage of BERT feature	75
9. FAQ	
10. Miscellaneous topics	
10.1. Revision History	
10.2. Disclaimer	
10.3. License	
10.4. Inquiry	
10.T. HIQUITY	∪∠

1. Introduction

This document is the user manual for TeliViewer. It is the tool for setup, image acquisition, and display for the camera products of Toshiba Teli, such as USB3/GigE/CoaXPress.

TeliViewer is available when TeliCamSDK is installed into your system since it is provided with TeliCamSDK package.

1.1. Terms

Following table explains the terms that are used in this document.

Term	Description
Main window	It is a centrally located window that displays images from the camera. Such a
IVIAIII WIIIGOW	window is called as "Main window".
Pane	It is a small window implemented for camera controls such as Discovery,
1 and	FeatureView, etc. Such a window is called as "Pane".
Stream	Image data form camera is called as "Stream", and operation to acquire the
Streaming	image is called as "Streaming".
Capture Rate	It is the frame rate (FPS) of currently acquiring the image from camera.
Display Rate	It is the frame rate (FPS) of currently displaying the image on Main window.
GEV	GigE Vision. It is a protocol supported by GigE cameras.
U3V	USB3 Vision. It is a protocol supported by USB3 cameras.
Plug-in	The operation of connecting a camera to a system is called as "Plug-in", and
Plug-out	the operation of removing a camera from the system is called as "Plug-out".
	This menu is displayed by right-clicking with the mouse on the window or
Context menu	pane. This allows users quick operations. Its usage will be explained in
	following sentences for each feature if it is available.
	The "2in1" mode divides the main window into two windows, allowing two
2in1 mode	camera images to be displayed, and the "4in1" mode divides the main window
4in1 mode	into four windows, allowing four camera images to be displayed at the same
	time.
	In "2in1" or "4in1" mode, the main window is divided into multiple areas. When
Current Area	a divided area is selected by clicking on it with the mouse, the selected area is
	encircled by red frame, and targeted for operation, called as "Current Area".
RW / RO / WO	They indicate the item's attributes as following.
TW/RO/WO	RW: ReadWrite, RO: Read-Only, WO: Write-Only
Hint	It explains regarding the recommended usage for users, or the supplemental
8	remarks for reference.
Attention	It explains regarding the issue that user should pay attention for using
	TeliViewer.

2. System Configuration

TeliViewer works with TeliCamApi that is provided by TeliCamSDK. If users need detailed information on system configuration, etc., refer to the "TeliCamSDK Start-Up Guide" or "TeliCamSDK for Linux Start-Up Guide".

3. Operation Environment

The basic requirements for the working environment are same as for the TeliCamSDK. For more details, refer to the "Hardware Requirements" and "Software Requirements" in the "TeliCamSDK Start-Up Guide" or "TeliCamSDK for Linux Start-Up Guide".

This section describes the TeliViewer specific requirements.

3.1. Regarding Streaming of Multiple Cameras

The "<u>Multi-Display</u>" feature described in the following section can stream multiple cameras at the same time. This is a useful feature since it allows users to view images from multiple cameras on a single screen at the same time, but it requires high hardware performance.

The recommended specifications for streaming multiple cameras simultaneously are following.

Recommended PC Specs	• CPU	: Intel Core i series 6th generation or later, 4 threads or more
	 Memory 	: 8Gbyte or more
	 Graphics 	: 2Gbyte or more VRAM with OpenGL support

Attention

Regarding the use of single board	Note that it is difficult to stream multiple cameras simultaneously on systems with low hardware specifications, such as the Raspberry Pi. Errors such as
computers such as Raspberry Pi	packet loss or else may occur and the expected performance may not be
	achieved.
	Even if your system meets the above recommended specifications, on the
Regarding the use of laptop PCs	laptop PC, there is a case streaming cannot be continued correctly. This
	depends on bandwidth of the data bus on the system, and if such bandwidth is
	insufficient, there is the possibility errors occur, such as packet loss. For this
	reason, it is recommended to use the desktop PC with sufficient bandwidth for
	data bus.

4. Installation

TeliViewer is installed with TeliCamSDK package. If it is required to know the detailed procedure to install the TeliCamSDK package, refer to "TeliCamSDK Start-up Guide" or "TeliCamSDK for Linux Start-up Guide".

5. Launch of TeliViewer

To launch TeliViewer, refer to the following procedures.

5.1. Windows

The procedures for Windows 10 are follows.

5.1.1. Launch from Start menu

[Procedure]

- 1) Press the Start button of Windows.
- 2) Open TOSHIBA TELI.
- 3) Select TeliViewer and launch it.

5.1.2. Launch from Search result

[Procedure]

- 1) Right-click the Windows Start button with the mouse.
- 2) Select "Search" from the menu.
- 3) Type "TeliViewer" as the search word.

.....

4) Select TeliViewer from the search result and launch it.

5.2. Linux

The procedures for ubuntu are follows.

5.2.1. Launch from Search result

[Procedure]

- 1) Click the "Activities" button on the taskbar or the "Show Applications" icon at the bottom of the Dock.
- 2) Type "TeliViewer" as the search word.
- 3) Select TeliViewer from the search result and launch it.

5.2.2. Launch from filer or terminal

[Procedure]


- 1) Open a filer such as Nautilus or a terminal, and then go to /opt/TeliCamSDK/bin.
- 2) Execute the script "execute_TeliViewer.sh" to launch TeliViewer.

DAA04027B

7

6. Structure of TeliViewer

The basic structure of TeliViewer is shown in the following figure.



The brief description of each component is following.

1) Menu bar

②Tool bar

By using these features, various operations are available for the camera and images. Details are explained in the following sections on each feature.

3 Main window

It is placed in the center of the TeliViewer to display the image from the camera. It also supports the feature of displaying images from multiple cameras simultaneously, such as "2in1" or "4in1". Refer to the detailed description within "Main window" section.

TeliViewer also has small windows for controlling the camera and images, or for displaying information. They are called as "Pane" and follows are supported in TeliViewer

4 Discovery

It supports features such as camera discovery, open/close the camera. Refer to the detailed description within "Discovery" section.

⑤FeatureView

It displays supported features within camera as the list. It is possible to confirm the current values or change the settings for each of features. Refer to the detailed description within "FeatureView" section.

6Status Log

It lists events that occurred on the TeliViewer. Refer to the detailed description within "StatusLog" section.

⑦Camera Control Panes

The most frequently used features for controlling the camera are collected into these panes. Refer to the detailed description within "Camera Control panes" section.



	By using DeviceUserID, user can set a unique ID for each camera. When several cameras are available in the system, this makes easier identifying
	the cameras. Also, since TeliViewer uses the DeviceUserID assigned to
Regarding the setting of	each camera as part of the key to identify them, this setting affects the
DeviceUserID	"Save/Restore Camera Settings" and "Save/Restore Line Drawing Status".
	Although this is not a requirement, in advance, it is recommended that
	DeviceUserID should be set appropriately.
	[Note] DeviceUserID can be set from "FeatureView".

7. TeliViewer features

This section describes the features supported by TeliViewer.

7.1. Discovery

It searches cameras that are available on the system and displays them in Camera List. By opening a selected camera from the list, the camera becomes available to operate.



7.1.1. Updating Camera List

When the button ① in above figure is pressed, the Camera List is updated. If any camera is newly plugged into the system, by pressing this button, it will appear in the list. Also, if any camera is plugged out, by pressing this button as well, it will be deleted from the list

7.1.2. Camera Open/Close

When the button ② is pressed, the camera selected on the Camera List can be opened or closed. The color of the button is changed as follows, according to the current state of camera.

Button state	Description
In case of (b)	The selected camera is closed. When this button is pressed, the camera will be opened.
In case of (U)	The selected camera is opened. When this button is pressed, the camera is closed.

7.1.3. Camera List

In the camera list ③ in above figure, cameras plugged into system are listed. By clicking the camera with the mouse or using the arrow keys on keyboard, users can select the camera to operate.



Regarding the display order of cameras	The cameras are listed in three categories, such as "U3V devices", "GEV devices" and "GenTL devices". In addition, cameras within each category are sorted and displayed in ascending order by ModelName + SerialNumber + DeviceUserID as the keys.
Using the context menu	If right-clicking with the mouse a camera in the list, it will open a context menu for opening/closing the camera. By using this, it is possible to perform quick operations equivalent to those described in ② above.
Plugged-in camera does not appear in the camera list	In such case, double-check whether connection between host and camera via the cable is correct, and then execute "Update Camera List". If it seems that there is no problem in camera connection, and the situation does not recover to correct state, refer to the support information on our website.

7.1.4. Open camera with external XML file



	This feature is intended for developers or specific users. If incorrect XML file is
About this feature	loaded, it may cause problems such as failure to configure the camera. So, it is
	required to pay attention for using this feature.

By right-clicking a camera in the list, the context menu will appear as following figure. By selecting this menu, the camera can be opened using an XML file stored in the local storage on the host.



By selecting this menu item, dialog to specify the XML file will be opened. Then, select the XML file and execute the steps to open the camera. Note that user must use correct XML file that matches to the current camera. Otherwise, the camera becomes out of control, as the result of loading incorrect XML.



In case incorrect XML file was	The camera will return from failure to correct state if camera is closed and
loaded	reopened, with procedure written in "Camera Open/Close".
Procedure for saving XML file	Refer to sentence within "Save XML to file".
from camera to local storage	

7.1.5. Features for GigE camera


The descriptions in this sentence are only available for GigE camera.

In the Camera List described as ③ above, by right-clicking a GigE camera with the mouse, that is listed in the "GEV devices" category, the following context menu will appear, and it is available to setup the GigE camera.

7.1.5.1. Access mode selection

It is available to select Access mode for a GigE camera with menu as following figure. Default setting is Control access. Basically, it is recommended to use with default setting.

If user need to change the settings by any reason, select the appropriate mode from following menu, and then execute the steps to open the camera.




Details of each mode are described in following table.

Access mode	Description
	Camera is opened with exclusive access rights. Then, registers on camera
Exclusive	can be accessed with RW permission. If it is opened with this mode, it
	becomes to be inaccessible from other hosts.
	Camera is opened with control access rights. Then, registers on camera can
Control	be accessed with RW permission. If it is opened with this mode, accessing
	from other hosts is limited with RO permission.
	Camera is opened with monitor access rights. Then, since registers on
	camera can be accessed with RO permission, this host cannot write and
	change any setting on camera. This mode should be used when the camera is
Monitor	already opened from other host, with the control access rights, and it is
	needed to access from this host to such camera, with RO permission.
	Basically, monitor access is used to open the camera as a listener, when
	" <u>Multicast</u> " is activated.

7.1.5.2. Launch "IP Configuration tool"

From following context menu, it is available to launch the external tool, such as "IP Configuration tool".



This allows users to change the IP address settings for the GigE camera on current network. Note that "IP Configuration tool" can change the settings of products of Toshiba Teli only.

7.2. Main window

Main window is a centrally placed window for displaying camera images. It supports various features to assist users, such as zoom in/out, drawing lines on the image, or etc. Also, it supports the "Multi display" feature, which allows to display multiple camera images on a single screen, such as 2in1/4in1.

The following descriptions explain how to use these features.

7.2.1. Control for stream

This section describes the operations for streaming from the camera. The basic controls can be operated from the toolbar as following.



7.2.1.1. Start

By pressing the button ① in above figure, streaming is started with current camera.

7.2.1.2. Pause


By pressing the button ② in above figure, updating of images is temporarily paused. Even if it is paused, capturing of images from camera is continued. This feature is useful when user need to confirm the actual capture rate from camera, without any overhead relating to image rendering.

If this button is pressed again, updating of images is resumed immediately.

7.2.1.3. Stop

By pressing the button 3 in above figure, streaming is stopped.





7.2.2. Scroll feature

When part of the camera image is outside the current display area, the scroll feature enables users to view and confirm the outlying image area. This feature is supporting 2 modes as follows. Users can select appropriate mode for current situation or preference. It is selectable on toolbar after stream is started.



7.2.2.1. Drag mode

By pressing the button ① in above figure, scroll mode will be changed to drag mode. When this mode is selected, users can scroll the image by following steps.

Additionally, if this button is pressed again, the drag mode will be turned off.


[Steps]

- 1) When the mouse cursor is on the camera image, confirm that the cursor shape is the same as the "palm" as shown in the above figure ①.
- 2) Click anywhere on the camera image with the left mouse button.
- 3) Move the mouse with dragging to scroll the image.
- 4) Release the left mouse button.
- 5) Move to the target coordinate by repeating the above steps 2 to 4.

7.2.2.2. Auto mode

By pressing the button ② in above figure, scroll mode will be changed to auto mode. When this mode is selected, moving the mouse cursor to any point on the camera image will bring automatically scrolling, in sync with the cursor movement.


Additionally, if this button is pressed again, the auto mode will be turned off.



7.2.3. Zoom feature

This section describes operations to zoom in or out the camera image. Basically, operations can be done from the toolbar. In addition to that, if a wheel-equipped mouse is connected to the host, user can also use this wheel to zoom in/out.

The available range for zoom is from 3% to 800%.



7.2.3.1. Using the slider

By dragging the handle (knob) with the mouse, on the slider ① in above figure, the value can be changed continuously. Also, by clicking on the guide areas, users can change the zoom setting in smaller steps.

The changed result is automatically reflected to ④ in above figure. By the value of ④, users can confirm the current actual value anytime.

7.2.3.2. Fit mode

By pressing the button ② in above figure, image is displayed with Fit mode. In Fit mode, the image is continuously displayed under the following conditions.

Image Direction	Display Effects
Vertical	Fit image to height of display area
Horizontal	Centering image to display area

Even if display area is resized, image will be displayed with above conditions. Additionally, Fit mode will be canceled forcedly, by pressing ①, ③, ④ in above figure, or the result of operating Ctrl key + mouse wheel, as described in this section.



9			
Using the context menu	When the camera image is displayed, right-clicking on the image area with the mouse displays a context menu for changing into the Fit mode, as shown in following figure.		
	By using this, it is possible to perform quick operations for changing into		
	by doing the, it is possible to perform quick operations for changing into		
	this mode.		

7.2.3.3. Actual size (100%)

By pressing the button ③ in above figure, image is displayed with actual size (Zoom: 100%).



8			
Using the context menu	When the camera image is displayed, right-clicking on the image area with the mouse displays a context menu for displaying the image with actual size, as shown in following figure.		
	◆ Zoom 100%		
	By using this, it is possible to perform quick operations for changing the		
	magnification to actual size.		

7.2.3.4. Using the spin box

By using the spin box ④ in above figure, it is available to enter values directly, or to change values in small steps using the spin buttons.

If value is changed by this method, the changed result is automatically reflected into ①.

7.2.3.5. Using the Ctrl key + mouse wheel

[Note] It is required a wheel-equipped mouse to accomplish this operation.

After clicking on an image area, the image can be zoomed in or out by holding down the Ctrl key on keyboard and moving the mouse wheel up or down.

Operation	Effects
Ctrl key + mouse wheel Up	Zoom in the image
Ctrl key + mouse wheel Down	Zoom out the image


7.2.4. Save image to file

The currently displayed image can be saved as a still image. To save the image, click the following button on the toolbar.




7.2.4.1. Dialog for save

By pressing the button 1 in above figure, following dialog will appear.




7.2.4.2. Save the lines on image

When Grid or 4x4 is enabled with "<u>Draw lines on image</u>" setting, check box ② in above figure is available. By checking it, the lines drawn on current image can be saved to a file,.



7.2.4.3. Setting for save

By pressing the button ③ in above figure, the dialog as following is displayed. In this dialog, it is available for users to select the folder, filename, and file format.



7.2.4.4. Folder

By using ④ in above figure, users can select the folder on the host, where the file is to be saved.

7.2.4.5. Filename

By using ⑤ in above figure, users can specify the filename to be saved. Initially, the filename is shown in "Image_yymmdd_hhmmss" style.

(yymmdd: Date when ③ was pressed; hhmmss: Time when ③ was pressed)

7.2.4.6. File format

By using (6) in above figure, users can select a format from 4 types in following table.

Format	Description
PNG	Image is saved as PNG format. Bit depth can be selected from 8, 16, 24, 32, or 48 bpp.
JPG	Image is saved as JPG format.
ВМР	Image is saved as BMP format. Bit depth can be selected from 8, 24, or 32 bpp.
RAW	Image is saved as RAW format.

7.2.4.7. Header of RAW format

When the image is saved with RAW format, the beginning of the saved file contains 32 bytes of header information as follows. The actual image data is stored immediately after it.

Structure	Size (Byte)	Description
Flag	4	0x00574152 indicating RAW format is always stored.
File size	4	Size of this file.
Image format	4	Image format stored in this file.
Width	4	Width of image.
Height	4	Height of image.
Reserved	12	This field is reserved for future extension.

7.2.4.8. Save button



Hint

Working with trigger mode

By using the trigger mode, user can explicitly capture the still images. If necessary, user can use it within "Trigger" pane of "Camera Control panes".

7.2.5. Loupe

Loupe tool is available to enlarge the part of image. It enlarges as doubled size of the image, in current cursor position.






7.2.5.1. Launch of Loupe

By pressing the button ① in above figure on toolbar, Loupe tool is launched. Loupe is moved in sync with current mouse cursor. When this button is pressed again, Loupe is closed.

Following figure is showing the overview when it is enabled, and image is enlarged.





Hint

Using context menu

When the camera image is displayed, right-clicking on the image area with the mouse displays a context menu for launching the Loupe, as shown in following figure.



Oupe

By using this, it is possible to perform quick operations for it.

7.2.6. Draw lines on image


This feature is available for drawing the lines on current image. By selecting the menu ① on menubar, or button ② on toolbar as following figures, users can draw them. The same dialog will appear for both selections.



The above operation opens the "Grid/4x4 Settings" dialog, and the usage for each of "Grid" and "4x4" is following.

7.2.6.1. Grid

By selecting the "Grid Settings" tab on the "Grid/4x4 Settings" dialog, the following dialog will appear. In addition, the image on the right shows the actual image with the Grid lines, according to the current settings. The width of lines is fixed as 1Pixel.



1 Draw Grid check box

When it is checked, Grid lines are drawn on current image.

2 Horizontal Pitch

It specifies the pitch of horizontal lines. The unit of the value is pixel.

③Vertical Pitch


It specifies the pitch of vertical lines. The unit of the value is pixel.

4 Color

When this button is pressed, the dialog for selecting the color is displayed. Users can change the color of them by it.

7.2.6.2. 4x4

By selecting the "4x4 Settings" tab on the "Grid/4x4 Settings" dialog, the following dialog will appear. By using this feature, four horizontal lines and four vertical lines can be drawn on the image. In addition, the image on the right shows the actual image with the 4x4 lines, according to the current settings.



1) Draw 4x4 check box

When it is checked and additionally following ② or ③ is checked, each 4x4 lines are drawn on current image.

②H1 \sim H4 (Horizontal Line #1 \sim #4) check box

When it is checked, horizontal line is drawn. After checking the above "①: Draw 4x4 checkbox", check any of H1~H4 to draw the corresponding horizontal line.

 $@V1\sim V4$ (Vertical Line #1 \sim #4) check box

When it is checked, vertical line is drawn. After checking the above "①: Draw 4x4 checkbox", check any of V1~V4 to draw the corresponding vertical line.

4 Position

It can specify the position of each line. The unit of the value is pixel. The setting and effects for horizontal and vertical lines are following.

Position setting	Effects
H1∼H4	Draw the horizontal line according to current setting, for position based on the upper left corner
H1/~H4	of the image. It is drawn on specified pixel position toward Y-axis.
V1~V4	Draw the vertical line according to current setting, for position based on the upper left corner of
	the image. It is drawn on specified pixel position toward X-axis.

(5) Width

It specifies the width of each line. The unit of the value is pixel. The available range is from 1 to 10.

6 Color

When this button is pressed, the dialog for selecting the color is displayed. Users can change the color of them by it.

7.2.6.3. Move 4x4 by mouse drag

Each 4x4 line drawn in the image can be moved by dragging with the mouse. Refer to the following procedure to move them.

[Steps]

- 1) Draw 4x4 lines according to the "4x4" procedure described in the previous section.
- 2) Move mouse cursor on 4x4 lines drawn on image.
- 3) Click the line with left mouse button and drag to move it.
- 4) When it has finished to move the line to the desired position, release the left mouse button.
- 5) With the above operations, the line can be moved to any desired position on the image.

Λ

Attention

Under the drag mode

This feature is not available under the "<u>Drag mode</u>". Drag mode should be disabled to use this feature.


g Hin

-		
	When the camera image is displayed, right-clicking on the image area with the mouse displays a context menu as following.	
Using context menu	Draw Grid	
	✓ Draw 4x4	
	Grid/4x4 Settings	
	1) Draw Grid	
	Grid can be turned on and off by this. The effect is the same as if	
	the operation ① had been done in the "Grid" description.	
	2) Draw 4x4	
	4x4 can be turned on and off by this. The effect is the same as if	
	the operation ① had been done in the " <u>4x4</u> " description.	
	3) Grid/4x4 Settings	
	"Grid/4x4 Settings" dialog can be opened.	
	By using this, it is possible to perform quick operations for Grind/4x4.	
	When the check box of "Save and Restore Grid/4x4 settings" in options	
	dialog is checked, it is enabled to save and restore current line drawing	
	states. Saving the settings is executed when the camera is closed, and data is saved into "Line configuration file".	
	Also, data is restored when the camera is opened. If a "Line configuration	
Regarding save and restore	file" exists that matches the three keys "ModelName / SerialNumber /	
Grid and 4x4 settings	DeviceUserID" of the current camera, it will be restored.	
	Attention	
	Note that if the DeviceUserID of the camera is changed, it will no longer	
	match the DeviceUserID stored in the "Line configuration file". As the	

result, previously saved data will not be restored.

7.2.7. Tab control

When the screen is displayed in normal mode (not multi-display) and multiple cameras are opened, tabs as following figure will appear at the top of the display area. This section describes the operation for tabs.



7.2.7.1. Change current camera

By left-clicking on a tab with the mouse, camera selection can be changed.

7.2.7.2. Tab detachment


Tabs can be detached by double-clicking on them. As the result, camera image is displayed with independent window. By utilizing this feature, the image display area can be arranged in a layout for user's preferences.

Also, double-clicking on the title bar of a detached window will re-tab it and return it to its original state.

7.2.8. Multi display

By clicking the "Multi-Display" on menubar, it is available to utilize 2in1 or 4in1 mode as following figure. By selecting one of these options, multi-display mode will be activated.

In following figure, 2in1 is checked and the viewer is working in 2in1 mode. If this is clicked again, the checked state is cancelled, and TeliViewer returns to normal mode. This operation is same for 4in1.





Attention for changing mode	Note that if the mode is changed when the camera is open, all opened cameras will be forced to close.	
Regarding the requirements for Multi-Display mode	Streaming multiple cameras with "Multi-Display" modes simultaneously requires	
	high hardware performance. Please refer to the description in "Operation	
	Environment" for requirements, etc.	


7.2.8.1. 2in1

By selecting ① in above figure, TeliViewer will enter into 2in1 mode. In 2in1 mode, two camera images can be displayed simultaneously in the main window.

The following section describes the procedure for displaying camera images in 2in1 mode.

[Steps]

1) By using the mouse, select any of the divided image display areas. The selected area (Current Area) is encircled by a red frame.



- 2) Open the camera to the Current Area according to the procedure "Camera Open/Close" in Discovery.
- 3) Start streaming to the opened camera in the Current Area with the "Start" procedure of the stream operation.
- 4) By using the mouse, select the area where the camera is not open and change the Current Area.
- 5) Repeat steps 2) to 4) above to start streaming for all cameras for which images are to be displayed.


7.2.8.2. 4in1

By selecting ② in above figure, TeliViewer will enter into 4in1 mode. In 4in1 mode, four camera images can be displayed simultaneously in the main window.

The following section describes the procedure for displaying camera images in 4in1 mode.

[Steps]

1) By using the mouse, select any of the divided image display areas. The selected area (Current Area) is encircled by a red frame.



- 2) Open the camera to the Current Area according to the procedure "Camera Open/Close" in Discovery.
- 3) Start streaming to the camera in the Current Area with the "Start" procedure of the stream operation.
- 4) By using the mouse, select the area where the camera is not open and change the Current Area.
- 5) Repeat steps 2) to 4) above to start streaming for all cameras for which images are to be displayed.



Using context menu	Quick operation for camera open	When the camera is not open, right-clicking on the Current Area displays the Camera Open menu as following. BU302LMCF 0000000 U3V #001 BU302MG 0310275 U3V #002 Update camera list By using this, it is possible to perform quick operations for opening the camera. Even in full screen mode, where the Discovery pane is not displayed, this can be used to open the camera.
	Quick operation for camera close	When the camera is open, right-clicking on the Current Area displays the Camera Close menu as following. Close By using this, it is possible to perform quick operations for closing the camera. For example, if users want to change the positioning of the camera while in full screen mode, users can use this and the open context menu as above to change it easily.
	Focusing the display on a specific camera in 2in1/4in1 mode	When the camera image is displayed, right-clicking on the image area with the mouse displays a context menu as following. Show full screen By using this, the current image can be displayed alone in full screen mode. Use this option when users want to focus on a specific image.
How to display or hide the scroll bar	each of the divided imag	rollbar" description for the scroll bar display settings within
How to display or hide the current frame rate, coordinate information, and RGB values	=	lay, " <u>TabBar</u> " or " <u>Overlay</u> " can be selected. It is possible able method according to user's preferences.

7.2.9. Full Screen display

By pressing the Full Screen button on the toolbar, the image can be displayed in Full Screen mode.



7.2.9.1. Start Full Screen

By pressing ① in above figure, the current main window can be displayed in Full Screen. It is available in following conditions.

Display mode	Effects
Normal	When the camera image is displayed in normal mode, pressing ① will display the current image in Full Screen.
2in1	When the camera image is displayed in 2in1 mode, pressing ① will
	display the 2in1 image in Full Screen.
4in1	When the camera image is displayed in 4in1 mode, pressing ① will display the 4in1 image in Full Screen.


7.2.9.2. End Full Screen

When the ESC key is pressed, the Full Screen returns to the previous screen.

25


7.2.10. Image Settings

By selecting the [Image] → [Settings] option in menubar, Image Settings dialog will appear as following. In this dialog, configuration settings for image rendering can be changed.



7.2.10.1. Bayer convert option

When the image format is Bayer type, pixel interpolation method can be changed with this option. It is possible to select from three types: Bi-Linear, ACPI, or No conversion. Default setting is Bi-Linear.



7.2.10.2. Interpolation display method

When the image is zoomed in or out, pixel interpolation method can be changed with this option. It is possible to select from two types: Nearest neighbor or Bi-Linear. Default setting is Nearest neighbor.

7.2.10.3. Set maximum display rate

It is possible to set the upper limit of the Display Rate. For example, in environments with low hardware performance, when the Capture Rate does not achieve the maximum camera FPS, it is typically due to system resources being drained by stress from the image rendering. In that case, by limiting the upper limit of the Display Rate, users can ensure that "maximum Display Rate with keeping the maximum Capture Rate" in current environment.

Specifically, refer to the following procedure.

[Steps]

- 1) Check the check box of "Set maximum display rate"
- 2) Input Zero to spin box
- 3) Confirm the Capture Rate
- 4) Increase the value of the spin box in small steps by about 1 or 2
- 5) Repeat steps 3 through 4 above to find a Display Rate that can keep the maximum Capture Rate


[Note] The maximum value that can be set here depends on the refresh rate of the monitor hardware currently in use.

7.2.10.4. Image display mode

It is possible to select the method to display the image from following 2 options. Default setting is High performance mode. Basically, please use with default setting. Regarding the utilization of Legacy mode, please understand the following descriptions and limitations.

Image display mode	Effects
High performance mode	This option realizes the high performance rendering of images with OpenGL. However, as following hint description, since it is affected by a value of GL_MAX_TEXTURE_SIZE, it has possibility that large image size cannot be rendered.
Legacy mode	This option doesn't utilize the OpenGL. So, performance of rendering is lesser than High performance mode. However, as following hint description, since it is not affected by a value of GL_MAX_TEXTURE_SIZE, it is possible to render the larger image size than High performance mode. Also, in this option, only CPU mode is available in "Image Processing".





7.2.10.5. Image processing

It is possible to select whether the image conversion is to be processed by the CPU or the GPU. Default setting is GPU.

Basically, by processing the images in GPU mode, the CPU stress can be kept low. As the result, the impact on other processes is reduced, and the entire system may be run more smoothly. So, it is recommended that users should work with GPU mode. Only if user meet any problem in displaying images while using the GPU mode, it is recommended to switch to the CPU mode as the workaround and confirm whether there is any improvement.

[Note] In some environments such as graphic driver without OpenGL support is installed, users cannot select the GPU mode. In that case, it will automatically work in CPU mode.




In case there is no difference in CPU stress between GPU and CPU mode

If inappropriate driver is installed for the graphics card, there is a possibility that the GPU processing will not work correctly. For information on how to install the most appropriate driver, refer to the website of vendor of graphics card.

7.3. FeatureView

This displays a list of features supported by the camera that is currently opened. It displays the current value of each feature and if it is editable, provides a method for editing.

FeatureView is consisted with the ToolBar, FeaturesList, FavoritesList, and Description area. The following section describes the usage of these components.



7.3.1. **ToolBar**

ToolBar is consisted with following features. This section describes how to operate each of them implemented here.



7.3.1.1. Reload

By pressing ① in above figure, the FeaturesList and FavoritesList will be updated to the current value.

7.3.1.2. Format Selection

By selecting ② in above figure, the display format of the FeaturesList can be changed as follows.

Buttons	Effects
button	Display by category.
å↓ button	Sort and display in alphabetical order

7.3.1.3. Filter Selection

By changing the selection of ③ in above figure, it is possible to filter the items that are displayed in FeaturesList. Each item supported by the camera has the attribute of Beginner/Expert/Guru, and the display of FeaturesList can be switched by selecting one of the follows.

Display Mode	Effects
B button	Beginner mode.
	It displays the items only for Beginner.
E button	Expert mode.
	It displays the items for Beginner and Expert.
G button	Guru mode.
O	It displays the items for Beginner, Expert and Guru.

7.3.1.4. Enable FavoritesList

By pressing ④ in above figure, toggles the FavoritesList pane ON or OFF. When it is ON, FavoritesList is available.


7.3.1.5. Save/Load camera features

By pressing ⑤ in above figure, submenu for saving or loading the settings of camera features will appear as following figure. This section describes how to use them.




7.3.1.5.1. Load features

By selecting (A) in above figure, following dialog is opened. It is possible to load the camera settings by selecting a file that was previously saved in the "Save features" steps.




Attention



7.3.1.5.2. Save features

By selecting (B) in above figure, the camera settings can be saved into a file with following dialog.



> Filename

(C) displays the initial string of file names. The string is constructed from "(ModelName)_(Serial Number)_(DeviceUserID)". If needed, the name can be changed to another one according to user's preferences.

> File format

In (D), only the tcf (TELI camera features) format can be selected. Only this format can be loaded by steps (A) in above description.



Attention

Under the CoaXPress, there are two types of settings: those belonging to the camera and those belonging to the capture board. Note that only the limited number of capture board settings will be saved into the file but not all settings.

7.3.1.6. Save XML to file

By pressing ⑤ in above figure, submenu for saving the XML file is displayed. It allows users to save XML data of currently opened camera into the file.



By selecting (C) in above menu, dialog for saving the XML file is displayed. Then, select the filename and folder, and click the [Save] button to save the file.

7.3.1.7. Access module selection

[Note] This feature is only available when current camera is GenTL device. When current camera is USB3 or GigE, it is N/A.

By changing the selection of (a) in above figure, the setting items for each module can be selected.

Items	Description
RemoteDevice	Displays items categorized as RemoteDevice.
	They are settings for the camera.
System	Displays items categorized as System.
	They are settings for the capture board.
Interface	Displays items categorized as Interface.
	They are settings for the capture board.
Device	Displays items categorized as Device.
	They are settings for the capture board.
Stream	Displays items categorized as Stream.
	They are settings for the capture board.

7.3.1.8. GenlCam cache setting

By changing ⑦ in above figure, the GenlCam cache can be turned ON or OFF.

This is a setting for developer. Default setting is ON. Basically, it should be left ON.

For example, if it is needed to reflect the current value in the FeaturesList or FavoritesList after writing the value directly to the camera register, by using the Write command, turn off this check box and then press the Update button ①. By this operation, the current value stored in the camera register can be directly read out, instead of the value stored in the cache.

[Note] If it is used with the OFF setting, I/O performance with the camera may be slower.

7.3.1.9. String search


By entering the string into 8 in above figure, it will search the items in FeaturesList with case-insensitive condition. In FeaturesList, all items that partially contain the entered string are searched, and the search results are displayed.

7.3.1.10. Delete button for string search

By pressing the button (9) in above figure, the all text entered into the string search will be deleted. Also, pressing Ctrl key + Del button works as a shortcut key for this feature.

7.3.2. FeaturesList

The supported features in current camera are displayed as following list.



7.3.2.1. Color of feature in list

Each feature in the list is displayed in a different color. The meaning of each color is following.

Color	Details
Black	Indicating that the attribute of the item is RW (ReadWrite). The value can be edited.
Brown	Indicating that the attribute of the item is RO (Read-Only). The value cannot be changed.
Green	Indicating that the attribute of the item is WO (Write-Only). When an editor for this feature is opened, a command button will appear.

7.3.2.2. How to change the value

If the attribute of the feature is RW or WO, it can be edited by opening a user interface for changing the value. This user interface is called as Editor. The following describes how to use it.

7.3.2.2.1. How to open/close the Editor

Editor can be opened or closed with following operation. When Editor is open, the value is editable.

Purpose	Operations
Open the Editor	Left-click the value with mouse With the feature on the "Name" column selected, press the right arrow key
Close the Editor	Left-click with mouse anywhere other than the opened editor Press Enter key Press ESC key


7.3.2.2.2. How to input to Editor

The following types of editors are available. This section describes how to change each value.

Type of Editor	Descriptions
Line editor	Integer values, floating-point values, and character strings can be entered directly. For GigE cameras, IP addresses can also be entered by it. The format of the values that can be entered depends on each feature. For details, refer to the instruction manual of current camera.
Drop-down list	By opening the editor, a list of selectable values is displayed. Users can select the value from it.
Command button	By pressing the displayed button, the selected operation is executed.
Composite editor	In this editor, both line editor and slider are available like following figure. Use these editors appropriately according to user's preferences. Hint Using the Tab key Additionally, instead of using the mouse, it is possible to switch the focus between the line edit and the slider by pressing the Tab key or Shift+Tab key. Height 1520 Changing the focus by Tab key

7.3.3. FavoritesList

By registering frequently used features into FavoritesList, users can quick access to them. The all features registered here will be restored at the next launch of TeliViewer.



7.3.3.1. Add feature

By selecting a feature on the "FeaturesList" and press ① in above figure, it will add the feature to the FavoritesList.

7.3.3.2. Remove feature

By selecting a feature on the FavoritesList and press ② in above figure, it will remove the feature from the FavoritesList.

7.3.3.3. Remove all features

If button ③ in above figure is pressed, all features in FavoritesList will be deleted.

7.3.3.4. Sort features

After selecting a feature on the FavoritesList, users can move it up or down, by clicking the up or down arrow button ④ in above figure. Items can be sorted in any order by user's preferences.

7.3.3.5. How to change the value

The method of editing a value is the same as on the FeaturesList. For more information, refer to "<u>How to change the value</u>".


7.3.4. **Description pane**

When any feature is selected on the FeaturesList or FavoritesList, detailed description of the feature will be displayed in this pane as following figure. If it is needed to know more about each feature, refer to it.

Description: Width (Integer node)
Width of the image provided by the device (in pixels).




	When mouse cursor is moved over the name in FeaturesList or FavoritesList, a
	tool tip will appear as following.
	Exposure T 8000.000000 us
	ExposureTime
Show tool tip ①	Sets the Exposure time when
(Feature name and description)	ExposureMode is Timed and
	ExposureAuto is Off.
	ExposureAuto is Oil.
	It is possible to see the entire name of a feature even if it is partially hidden. Also
	It is possible to see the entire name of a feature even if it is partially hidden. Also,
	a brief description of it will be displayed for reference.
	If a feature has the predefined value range, moving the mouse cursor to the
	Editor will display the Min/Max/Inc values as following.
Show tool tip ②	Width 2048
(Info for settable values)	Min = 64, Max = 2048, Inc = 4
(e iei eeitaale valaee)	THIN - S I THUX - LO ISI III - T
	14 in an all alta de la confirma de la companya de la confirma de
	It is available to confirm the range of values that can be set.
	By right-clicking a feature in FeaturesList, context
	menu is displayed as following.
Heim or a section to the section of	Add feature to Add to favorites
Using context menu	FavoritesList Add to ravorites
	It is possible to use it for quick registration to the
	FavoritesList.



7.4. StatusLog

It lists the events occurred in TeliViewer.



7.4.1. Clear Event list

When button ① in above figure is pressed, all events displayed in the event list will be cleared.

7.4.2. Event filter selection

By pressing any button ② in above figure, it is possible to filter the events displayed.

Filter	Effects
a button	Displays Error information. It corresponds to an event type of ERR . It is an error that prevents to continue the processing.
button	Displays Warning information. It corresponds to an event type of WRN. It is a warning that can continue the processing.
i button	Displays Info information. It corresponds to an event type of INFO. It is information but not error such as status change or else.

7.4.3. Details of Event list

In field ③ in above figure, each listed event is consisted with following information.

Item	Descriptions	
Data/Time	Indicates the date and time of the event.	
Camera	Indicates the ModelName, SerialNumber and DeviceUserID of the camera that the event occurred on.	
Туре	Indicates the type of event that occurred. As described in the previous section, there are three event types: ERR/WRN/INFO.	
Code	Indicates the event code.	
Message	Indicates the detailed description of the event.	

7.4.4. Save events

By pressing the button ④ in above figure, a dialog to save the all events currently displayed in ③ will be opened. It can save them into CSV file. User can use it to analyze them on demand.

7.5. Camera event

By this pane, event from camera can be retrieved and displayed. It can be opened by selecting [View] \rightarrow [Camera Control] \rightarrow [Camera Event] on toolbar.

```
Camera Event

1 2 3 4 5
2023-04-17 18:50:32:513, BU302MG 0310275 111, FrameTransferStart(0x8030), 0x1728f52f6176
2023-04-17 18:50:32:513, BU302MG 0310275 111, FrameTransferEnd(0x8031), 0x1728f58b19bc
2023-04-17 18:50:32:513, BU302MG 0310275 111, ExposureEnd(0x8041), 0x1728f59cde90
2023-04-17 18:50:32:513, BU302MG 0310275 111, ExposureStart(0x8040), 0x1728f59e2106
2023-04-17 18:50:32:513, BU302MG 0310275 111, FrameTransferStart(0x8030), 0x1728f5a08108
2023-04-17 18:50:32:518, BU302MG 0310275 111, FrameTransferEnd(0x8031), 0x1728f5c4920
2023-04-17 18:50:32:530, BU302MG 0310275 111, ExposureEnd(0x8041), 0x1728f60dfe22
2023-04-17 18:50:32:530, BU302MG 0310275 111, ExposureStart(0x8040), 0x1728f60f4098
2023-04-17 18:50:32:530, BU302MG 0310275 111, FrameTransferStart(0x8030), 0x1728f611a068
```

7.5.1. Clear camera events

When button ① in above figure is pressed, all events displayed in the event list will be cleared.

7.5.2. Turn ON/OFF camera event


By pressing the button ② in above figure, user can switch ON or OFF the camera event. The status of

button will be changed as follows as toggle.

Status	Effect	
S button	It means camera event is disabled. If the button is pressed, camera event becomes enable, and status of button will be changed as following.	
button	It means camera event is enabled. If the button is pressed, camera event becomes disable, and status of button will be changed as above.	

7.5.3. Select camera event

By pressing the button ③ in above figure, a dialog as following will be displayed. This dialog shows the available events in current camera. By checking each checkbox on dialog, user can select the camera event to be retrieved





Hint

Regarding the selectable event

The selectable event here is different in each camera model. If it is required to know the more detailed information for each event, users can confirm it with user manual for current camera. It can be downloaded from <u>our website</u>.



Attention

If several events are selected at the same time


The CPU load will be increased due to increasing the number of events received. As the result, the capture or display rate will be decreased. If user want to avoid this situation, please enable the minimum number of events required.

7.5.4. Save camera events in list

By pressing the button ④ in above figure, a dialog to save the all events currently displayed in ⑥ will be opened. It can save them into CSV file. User can use it to analyze them on demand.

7.5.5. Option settings

By pressing the button ⑤ in above figure, a dialog "Event Display options" as following will be displayed. User can configure the display settings for the events shown in ⑥ as follows.



	Item	Description	
1	Update interval of list	It specifies refresh interval of the list in milliseconds, which can be set between 100 and 3000 milliseconds. The default is 500 milliseconds.	
2	Maximum events in list	It specifies the maximum number of events to be displayed in the list, which can be set between 10 and 1000. The default is 200 events.	
3	Event display format	It specifies the event display format. User can select from any of the following. Code Displays event code only. String Displays the event name string. String + Code Displays the event name string and event code at the same time.	
 It specifies the timestamp d following. → Hexadecimal Displays in hexadecimal. → Decimal 		Hexadecimal Displays in hexadecimal.	

Attention

	If the setting value of ① is decreased or the setting value of ② is increased, the
Regarding settings ① or ②	CPU load for the list update process will increase. Note that, as a result, capture
	rate or display rate will be decreased.

7.5.6. Camera evet list

The events retrieved from the camera are displayed in ⑥, in the order which they were received. The one line displays the information for one event. The events are displayed in the following format.

[Date and time of event acquisition], [Camera identification], [Event], [Timestamp]

Item	Description	
Date and time of event acquisition	It indicates the date and time on the host terminal side at which the event was acquired.	
Camera identification	It indicates information to identify the camera that sent the event, consisting of ModelName + SerialNumber + DeviceUserID.	
Event	It indicates the event acquired from the camera. It is displayed in the format specified in ③ under "Option settings".	
Timestamp	It indicates the Timestamp information transmitted from the camera. The display format can be selected from either decimal or hexadecimal using ④ under "Option settings".	

7.6. Camera Control panes

TeliViewer is supporting Camera Control panes that provide the method for quickly accessing to frequently used features.

The following describes the explanation for using them and recommended usage.

7.6.1. Type of panes

The following type of panes are supported in TeliViewer.

Pane	Descriptions		
Image Format	PixelFormat, Width/Height and else can be controlled in this pane. It supports to control		
-	the features relating to Image Format.		
Image Correction	Gain, Gamma, WhiteBalance and else can be controlled in this pane. It supports to		
illage Collection	control the features relating to Image Correction.		
Color Macking	Color Masking can be controlled in this pane.		
Color Masking	[Note] This pane is only available for the camera that is supporting the Color Masking.		
Exposure	Exposure and relating features can be controlled in this pane.		
Acquisition	Acquisition and relating features can be controlled in this pane.		
Trigger and relating features can be controlled in this pane.			
UserSet	UserSet and relating features can be controlled in this pane.		
GEV Setting The features relating to GigE camera can be controlled in this pane.			
U3V Info	The information relating to USB3 camera can be shown in this pane.		
Register R/W	Register Read/Write can be executed in this pane.		

7.6.2. Display the details of feature

When mouse cursor is moved over the label of each feature, the details of feature will be displayed as the tooltip. Users can confirm the brief description for the feature by it.

For example, when mouse cursor is moved over the label of Gain, tooltip is displayed as following figure.






In case the more detailed information for each feature is required

If it is required to know the more detailed information for each feature, users can confirm it with user manual for current camera. It can be downloaded from our website.

7.6.3. Display the settable value range

When mouse cursor is moved over the slider of edit box of each feature, the value of Min/Max/Inc is displayed as following figure. Users can confirm the settable value range for the feature by it.

For example, when mouse cursor is moved over the Width, they are displayed as following figure. It is indicating settable value on camera as Min is 64, Max is 2048 and Inc is 4.





Regarding the Inc value

There is the case that feature doesn't support Inc value. Then, Inc is not displayed in settable value range.

7.6.4. Utilizing the Update Buttons

The following two Update buttons are available on toolbar in Camera Control panes. The descriptions for them are follows.



7.6.4.1. Update button

When the button ① in above figure is pressed, all features existing on current pane are reloaded, and updated with latest value on the camera.

For example, when the value of feature is updated from FeatureView, and even if such update will affect to the current value of any feature on Camera Control panes, it is not automatically reloaded into features on panes. Then, by pressing the button ① in above figure, it is available to manually reload the current value.

7.6.4.2. Auto Update button

The button ② in above figure is only available in Image Correction and Exposure pane. This button works with toggle. When it is enabled, the features in current pane are automatically and repeatedly reloaded with fixed interval.

If it is required to trace the specific value of some features, such as Gain, WhiteBalance or ExposureTime which its value is changed autonomously, this button will work effectively as the solution for users.

The update interval for Auto Update is 1000msec. In addition, if this button is pressed again, it becomes unchecked state and Auto Update is disabled.

7.6.5. Regarding grayed out features

If any feature placed in current pane is grayed out, it is indicating the feature is within one of the following states.

> N/A because of current camera state

There are some features such as PixelFormat, Width, Height or else which its value cannot be changed while camera is in streaming. Such features can be changed when streaming is stopped. So if streaming is stopped with steps in "<u>Stop</u>", the state of feature recovers from grayed out to normal and it will become able to change the value.

N/A because of relationship with other features

There is a case that the feature is grayed out relating to current setting of other features. For example, AcquisitionFrameRate is available when AcquisitionFrameRateControl is set to "Manual". When current value of AcquisitionFrameRateControl is other than that, it is grayed out and N/A.

N/A in current camera


If the feature is not supported in current camera, it is grayed out and N/A.



In case the detailed information for features supported in current camera is required If it is required to know the more detailed information for each feature supported in current camera, users can confirm it with user manual. It can be downloaded from our website.

7.6.6. Recommended usage

The panes implemented within TeliViewer can be used with tabified or multilayered into dock as following. By the operation of drag and drop with mouse, users can arrange the placement of them, for easy accessing to each feature, or according to user's preferences.



43 DAA04027B


7.7. Multicast

This feature described as follows is **only available for GigE camera**.

By this feature, it is available that multiple hosts can retrieve the images from one GigE camera.

7.7.1. Overview

The following figure shows overview and typical construction of network for using the Multicast.



	Devices	Descriptions	
1	GigE camera	GigE camera that will deliver the image using Multicast.	
2	Distributor	Typically, it is the device called as switch or router. It must be the device such as L3/L2 switch or router that is supporting Internet Group Management Protocol (IGMP) or IGMP Querier feature, for executing Multicast transmission.	
		It is a host system accessing to camera with RW access rights. It means that such host controls the camera, retrieves the image, and is called as Controller. In a Multicast group, only one host can act the role of the Controller.	
4	Listener	They are host systems accessing to camera with RO access rights and retrieving the image without controlling the camera. Such hosts are called as Listener. As above figure, multiple Listeners can exist in a Multicast group.	



Attention

Regarding the IP address settings for each device

It is required to apply appropriate IP address and subnet mask to communicate between each device. Regarding IP address assignment, etc., it is recommended to confirm with the administrator of the current network, before setting up.

7.7.2. Access Mode Setting

The access mode for each host must be set up as following table. Basically, users need not to care to change it since when the camera is opened, it is automatically decided by TeliViewer.


Hosts	Hosts Access Mode Details		
Controller Control		Open the camera with RW access rights	
Listener Monitor		Open the camera with RO access rights	

For instance, when the GigE camera is already opened from Controller, TeliViewer determines the 2nd or later host that try to open same GigE camera is Listener. Then, Monitor for Access mode is automatically selected for such hosts.

As the exception, in case a Listener open the camera before Controller, it is required to select Monitor for Access mode manually in Listener host. For changing the Access mode, refer to "Access mode selection".

7.7.3. Multicast Setting

By selecting the [View] \rightarrow [Camera Control] \rightarrow [GEV Setting] on menubar, following pane is displayed. In this pane, Multicast can be set up. The description for setting up each item is as follows.



	Items	Descriptions	
1	MaxPacketSize	Packet size for streaming with Multicast is specified in this field. It must be used as the common value for all hosts and camera, in a Multicast group. For details to decide such value, refer to "Determine MaxPacketSize".	
2	Access Mode	Current Access Mode is displayed in this field. In Controller, "Control" is displayed, and in Listener, "Monitor" is displayed.	
3	Enable multicast	By turning "ON" this, Multicast is enabled.	
4	Address	IP address for Multicast is set in this field. Default value is "224.64.16.1". It must be used as the common value for all hosts and camera, in a Multicast group. If it is needed to change, IPv4 multicast addresses defined by standards must be used. For details of standards, refer to RFC documents or else.	
\$	Port	Port number for Multicast is set in this field. Default value is "50506". It must be used as the common value for all hosts and camera, in a Multicast group. If it is needed to change, note that port numbers reserved as System Ports (or Well-Known Ports) are not available. For details of available port numbers, refer to the IANA website or other sources.	

7.7.4. **Details for Setup**

This section describes the specific setup procedures for Multicast.

7.7.4.1. Determine MaxPacketSize

First, the available MaxPacketSize for all hosts must be determined. Such value depends on the construction of a Multicast group. To determine it, the JumboPacket or Maximum Transmission Unit (MTU) size of all hosts in a Multicast group must be researched as follows.



In Windows, the JumboPacket can be set by opening the proper	
How to check/set JumboPacket the network adapter from the Device Manager. In Linux base	
or MTU size	MTU can be set using ifconfig, etc. For details, refer to the OS manual or
	ask administrator of current network.

As a result of research, if a Multicast group is constructed with following table:

Host	JumboPacket / MTU size	
Controller	9014	
Listener (A)	8192	Appropriate MaxPacketSize 4096
Listener (B)	4096	<u></u>

For MaxPacketSize, select the "maximum size that all hosts can receive".

So, in above example, appropriate MaxPacketSize is 4096. This value should be used in following steps for setup.

7.7.4.2. Setup for Controller

It is recommended that the Controller is configured first, and next the Listener.

The steps for setting up the Controller is as follows.

[Steps]

- 1) Launch TeliViewer in Controller
- 2) Open GigE camera with steps in "Camera Open/Close"
- 3) Open "GEV Setting". Then, confirm Access Mode is "Control"
- 4) Check the check box of Enable multicast
- 5) If it is needed to change the Address and Port, set them appropriately. If it is not needed to make any changes, users can use with default settings.
- 6) Set "Determined value" to MaxPacketSize
- 7) Start streaming with steps in "Control for stream"
- 8) Confirm the image from camera is displayed correctly

7.7.4.3. Setup for Listener

It is recommended that the Controller is configured before the Listener.


The steps for setting up the Listener is as follows.

[Steps]

- 1) Launch TeliViewer in Listener
- 2) Open GigE camera with steps in "Camera Open/Close"
- 3) Open "GEV Setting". Then, confirm Access Mode is "Monitor"
- 4) Check the check box of Enable multicast
- 5) Set the same values as the Controller for Address and Port
- 6) Set the same values as the Controller for MaxPacketSize
- 7) Start streaming with steps in "Control for stream"
- 8) Confirm the image from camera is displayed correctly

7.8. Waveform

This chart displays the luminance characteristics in current image.



The details for each item in this monitor are following.


	Items	Details	
1	Monitor	Luminance characteristics in current image is displayed.	
2	Color assortment	Specify the color assortment for monitoring. It can be specified the range from 0 to 255.	
3	Monitoring range	Specify the monitoring range. The range that can be specified depends on setting of ⑤ in this table and width or height in current image.	
4	Pause button When this button is pressed, update of monitor is paused.		
5	Direction setting	Specify the horizontal or vertical for monitoring direction.	
6	Data type	Specify the YUV or RGB for monitoring. By checking each check box, each component current image can be selected for monitoring.	
7	By pressing the Area button, it becomes into area-specified mode. Under this mode enabled to specify the limit of area for sampling. Sub line Three lines can be drawn on monitor by this. Intensity Intensity Intensity setting of each component can be changed on the monitor.		
8			
9			



Changing the update interval of monitor If it is needed to change the update interval of monitor, it can be changed with "<u>Updating interval of charts</u>" in options dialog.

7.9. Vectorscope

This chart displays the characteristics of chrominance components of U and V in current image.



The details for each item in this monitor are following.


	Items	Details
1	Scope	Displays the current characteristics in current image.
2	Current value	Displays the value of the mouse cursor position on the scope.
3	Pause button	By pressing this button, the update of the scope can be paused.
4	Intensity	Intensity setting of each component can be changed on the display.
5	Magnification	Magnification can be changed on the display.



Changing the update interval of	If it is needed to change the update interval of monitor, it can be changed
monitor	with "Updating interval of charts" in options dialog.

7.10. Histogram

This chart displays the distribution of pixel value in current image.



The details for each item in this monitor are following.

	Items	Details
1	Histogram	Current distribution of pixel values is shown as a chart. When the mouse cursor is moved over ①, the frequency of each data component selected in ⑥ is displayed as a tool tip.
2	Frequency (Y axis)	For each data component selected in ⑥, the frequency of appearance of each pixel value is shown. Maximum value of the Y axis changes dynamically according to the current image.
3	Pixel value (X axis)	It indicates the pixel value. The Maximum or Minimum pixel value depend on the current image format. The above figure shows an example, when RGB format is selected, displaying values from 0 to 255. When the mouse cursor is on the X-axis, the partial magnification is available by holding down the Ctrl key and moving the mouse wheel up/down.
4	Reset axes	It is available when the X axis is in the magnified state at ③. Pressing this button resets the magnification and returns to the normal scale state.
5	Statistics	It is available only when a single component is selected in ⑥. It displays the Mean, Standard Deviation, Minimum and Maximum values for the currently selected data component.
6	Component selection	It allows users to select the data component to be shown as a histogram. If the current image is mono format, only Y can be selected. If the image is in color format, all data components are available for selection. The above figure shows an example of selecting R, G, and B on a color image.

Hint

Changing the update interval of monitor If it is needed to change the update interval of monitor, it can be changed with "Updating interval of charts" in options dialog.

7.11. Save/Load camera features

By using the following buttons on the toolbar, it is available to save or load the camera features.



They are shortcuts to the feature implemented in FeatureView. For details on how to operate them, refer to the descriptions in "<u>Save/Load camera features</u>" section of FeatureView.

7.12. Video recording

This feature enables users to record the streaming images as the video into AVI or MP4 file format.



Attention

Regarding the available platforms

This feature is not available on platforms that use the ARM architecture, such as the Raspberry Pi.

7.12.1. Precautions for using this feature

Please use this feature if you fully understand and agree with the following precautions.

1) Regarding the video recording feature

TeliViewer uses GStreamer for the video recording feature. Users can use such feature by installing GStreamer into user's environment.

2) Regarding the recording videos to file

Users can choose either uncompressed (default) or compressed when recording the videos to file on TeliViewer. If users require the video to be compressed, it is possible by using the encoder.

3) Installation of encoders

By installing the GStreamer Plugin, users can use the encoder to record the videos on TeliViewer.

4) Regarding the selection of encoder

Each encoder has an individual license, and there is the case it contains patented technology. Users should select the encoder under user's responsibility and then must agree to follow the terms and conditions of the selected encoder.

5) In case of selecting any H.264 encoder

If users use a technology equivalent to the H.264 standard for video compression, users must agree to the following terms and conditions:

https://www.mpegla.com/wp-content/uploads/avcweb.pdf

[Note]

For further details, such as the "Where End User pays for AVC Video" clause, users should refer to the applicable terms and conditions in above documentation.

6) Regarding the workings of encoder

This document describes reference procedures for using the encoder on TeliViewer. However, please note that it does not guarantee that the encoder will work correctly on demand of users.

7) Regarding the following usage procedures

The following contents are reference procedures when this document was prepared, and information regarding the URLs and installation procedures are subject to change depending on the circumstances of the module distributor. Even if there are any points in the following procedures that do not correspond to the current situation, users have to solve them by themselves by using internet searches, etc.

8) Disclaimer

- > Our company is not responsible for any problems that users meet as a result of using the encoder. Please contact the encoder distributor for any problems when using the encoder.
- Our company is not concerned with any licensing or patent issues arising from the choice by users made in 4) above.
- Our company is unable to answer to any questions from users about the encoder.

7.12.2.Installation of GStreamer

To use this feature, users need to install GStreamer into user's environment according to the following procedure.

7.12.2.1. Windows

To use the GStreamer package on the Windows environment, users need to follow the instructions below to download, install and properly configure the path to the GStreamer package.

If users are unclear about anything in the explanations in this manual, please also check the links below for further information.

[GStreamer: Installing on Windows]

https://gstreamer.freedesktop.org/documentation/installing/on-windows.html?gi-language=c

7.12.2.1.1. Download of GStreamer package

Download the "runtime installer" that matches user's environment from the link below. https://gstreamer.freedesktop.org/download/

7.12.2.1.2. Installation of GStreamer package

Launch the downloaded installer and install GStreamer. Depending on the installation option that the user selected, the configuration of the installed Plugin will differ. For more information, please refer to the GStreamer user manual.


7.12.2.1.3. Configuration of path

After installing GStreamer, users need to configure the path settings to make it available from TeliViewer. Please refer to the following instructions to set up the path.


The following procedure describes the case of installation to the default installation folder "C:¥gstreamer" as an example. Please note that if user install to a location other than the default, user need to set a different folder path to the one described in the following procedure.

[Steps]


- 1) Right-click the Windows Start button
- 2) Select [System] from the menu that appears
- 3) Scroll downwards in the opened window and select [Advanced system settings]
- 4) Select the [Advanced] tab and press the [Environment Variables] button
- 5) The dialog box shown below is displayed, select the [Path] row and press the [Edit] button



6) The dialog box shown below is displayed and press the [New] button



7) When the path input mode will be entered, set "C:\footnotes the OK button and save. If the installation destination is changed to another folder different from the default in the installation procedure, set "\Destination folder\footnotes 1.0\footnotes msvc_x86_64\footnotes bin"



- 8) Press the OK button to close [Edit environment variable] dialog box
- 9) Restart Windows to reflect the changes to the entire system

7.12.2.2. Linux based OS


Please refer to the links below for further information.

[GStreamer: Installing on Linux]


https://gstreamer.freedesktop.org/documentation/installing/on-linux.html?gi-language=c

7.12.3. Video recording settings

- 1) Open the camera to which user want to record the video
- 2) Select [Recording] → [Settings] from the menubar as shown below



3) As the result, the dialogue box shown below will open. Users can configure the settings for the video file to be saved



7.12.3.1. File path

By setting the ① in above figure, users can select the destination folder for the video file. Default folder is as follows:

os	Folder
Windows	%HOMEPATH%Videos
Linux based OS	\$HOME/Videos

Hint

Selection of the storage medium on which to save the video

The video recording feature is affected by the write speed supported by the storage medium selected as the storage destination. If the write speed to the storage medium is slow, this can cause problems such as dropped frames when writing. If the user wishes to save videos with higher quality and reproducibility, it is recommended to select a storage medium that supports high-speed writing, such as M.2 or SSD, as the video storage destination.

7.12.3.2. File name

By setting the ② in above figure, Users can specify the name of the file in which the video is to be saved. Initially, the filename is shown in "Video_yymmdd_hhmmss" style.

(yymmdd: Date when video record start was pressed; hhmmss: Time when video record start was pressed) If the user wants to specify a file name other than this, uncheck the ② and enter the name of the file to be saved in the edit box.

7.12.3.3. File format

Users can select the format of the file to be saved from any of the following. Select the most suitable format according to the playback method to be used.

In addition, if users choose to save videos in uncompressed format, AVI will be automatically selected.

Format	Description
AVI	Save videos in AVI format.
MP4	Save videos in MP4 format.

7.12.3.4. Use encoder

By checking ④ in above figure, the list of available encoders in the current environment will be displayed. Users can use several encoders on TeliViewer, that are installed with GStreamer installation. By selecting an encoder from the drop-down list, users can save the compressed video to a file.

If ④ is not checked, the video is saved in uncompressed format. Default is uncompressed.



Hint

	The encoders that can be selected is depending on the operating system and distribution currently in use, or on the installation options specified
	when GStreamer was installed. If it is necessary to find out information
Regarding the encoders that	on each of the available encoders, please use an internet search or
appear in the drop-down list	something similar to confirm the information.
	Additionally, in some environments, the hardware encoder is available. In
	this case, selecting a hardware encoder is likely to result in low-load
	video recording.

7.12.3.4.1. Threads setting

As a result of checking ④ and selecting an encoder, if the number of threads used for compression can be changed by the currently selected encoder, this menu is enabled. Increasing the number of threads used will reduce the time taken for compression but will increase CPU utilization. Decreasing the number of threads used increases the time taken for compression but decreases CPU utilization.

7.12.3.5. Limit Max video frame rate

By checking ⑤ in above figure, it is possible to limit the maximum frame rate saved in a video file. This can work as effective workaround when users want to avoid video files becoming bloated.

The range of available values depends on the current "AcquisitionFrameRate" setting of the camera.

7.12.3.6. Limit Max frame to save

By checking ⑥ in above figure, it is possible to limit the maximum number of frames that can be saved to a video file. Users can use this function if it is necessary to end video recording when a specific number of frames have been saved, without unlimitedly continuing to save the video.

7.12.3.7. Optimization for uncompressed video

If 4 is unchecked, the video is recorded in uncompressed format. Then, the menu item 7 is activated and users can select a setting from one of the following options.

Setting	Description
Scale down FPS	Optimizes the frame rate (automatic frame decimation) when writing images to video files and saving them.
Scale down image size	Optimizes the image size (automatic size shrinking) when writing images to video files and saving them.



Hint

When recording image data received from the camera as video in uncompressed format, the capacity is generally larger than for encoded video. Although it depends on the write speed of the destination media, in many cases it can lead to problems such as dropped frames due to overcapacity, users may have the likelihood of not achieving the desired video recording deliverables as the result. As the workaround, TeliViewer uses whichever option is selected here to optimize the writing speed to the media to around 150 MB/sec when recording the videos in uncompressed format. Such procedure brings the result in smooth playback of the recorded video.

7.12.4. Recording the video

It can be operated from the toolbar on the TeliViewer to start/stop video recording.

7.12.4.1. Start recording

- 1) Start streaming from camera.
- 2) Press the button shown below, located on the toolbar. Then, video recording will be started.



3) Please wait until the required recording time.

7.12.4.2. Stop recording

1) Press the button shown below, located on the toolbar. Then, video recording will be stopped.



2) The recorded video is saved to file specified with "File name" into the location specified with "File path".



Attention


	During the video recording, if disk full occurred within storage, it will be automatically
Regarding the behavior when	stopped with displaying the message "No space left on the resource". Before starting
disk full occurred	the recording, it is recommended to confirm there is enough free space in storage in
	advance.

7.13. Snapshot Recorder


This feature enables users to continuously save streaming images as still images. It is available exclusively on Windows. Furthermore, this feature cannot be used in Random Trigger Shutter mode."

7.13.1. Snapshot Recorder Settings

- 1) Open the camera to which user want to save the still image
- 2) Start the stream.
- 3) Select [View] → [Snapshot Recorder] from the menubar as shown below



4) As the result, the dialogue box shown below will open. Users can configure the settings for the still image file to be saved.



7.13.1.1. Folder Path

By setting the ① in above figure, users can select the destination folder for the still image file. Default folder is as follows:

os	Folder
Windows	%HOMEPATH%Pictures



Selection of the storage medium on which to save the still image

The Snapshot Recorder feature is affected by the write speed supported by the storage medium selected as the storage destination. If the user wishes to save still image at a higher speed, it is recommended to select a storage medium that supports high-speed writing, such as M.2 or SSD, as the still image storage destination.

7.13.1.2. File Name

By setting the ② in above figure, Users can specify the name of the file in which the still image is to be saved. Initially, the filename is shown in "Image_yymmdd_hhmmss_number" style. (The "number" part is a sequential number.)

(yymmdd: Year, month, and day when the still image was acquired; hhmmss: Hour, minute, and second when the still image was acquired.)

If the user wants to specify a file name other than this, enter the desired filename in the edit box labeled "Prefix". Also, if the user does not need _yymmdd_hhmmss in the file name, uncheck ③.

If the user unchecks ③, the name of the saved file will be "Image_number". (The "number" part is a sequential number.)

When Recording Mode is set to "Frame Count Repeat", 4 is available.

If the user unchecks ④, the value of 'number' will not be reset.

If the user checks ④, the value of 'number' will be reset.

Please refer to Recording Mode for information on Recording Mode.

7.13.1.3. File Format

By setting the ⑤ in the above figure, users specify the file format to save as a still image.


Setting	Description
ВМР	Save the image as a Bitmap file.
JPG	Save the image as a JPEG file.

7.13.1.4. Recording Mode

By setting the 6 in the above figure, users can select the mode. There are two types of modes available.

Setting	Description
Frame Count	Save images of a specified number of still frames. Once the first image is acquired from the camera, the process of saving the image to the storage medium is initiated. Additionally, when the specified number of frames is reached, the process of acquiring images from the camera and saving them to the storage medium will cease. Please refer to Frame Count for setting the specified number of frames.
Frame Count Repeat	Execute the operation of the "Frame Count" mode repeatedly. Once the first image is acquired from the camera, the process of saving the image to the storage medium is initiated. Additionally, the Frame Count operation is executed at specified time intervals. Please refer to Frame Count for setting the specified number of frames. Please refer to Repetition Cycle for setting the repetition interval.

The operation of each mode is as follows.



7.13.1.5. Frame Count

By setting the \bigcirc in the above figure, users can specify the number of still images to save. This value is used in "Frame Count" and "Frame Count Repeat" modes.

7.13.1.6. Repetition Cycle

By setting the \otimes in the above figure, you specify the time interval for obtaining images from the camera. This becomes available in "Frame Count Repeat" mode, and this value is utilized.


By checking the ③, users can stop the operation of acquiring images from the camera and saving images to the storage medium at the specified interval. If users uncheck ⑤, please use <u>Stop Image Acquire (Stop Image Saving)</u> to halt the operation.

7.13.1.7. Start Image Saving

By pressing button (10), the system initiates the process of acquiring images from the camera and saving them to the storage medium.



Attention



7.13.1.8. Stop Image Acquire (Stop Image Saving)

Pressing button ① will stop the operation of acquiring images from the camera and saving images to the storage media. Additionally, pressing the "Stop Image Acquire" button will change to the "Stop Image Saving" button. When the "Stop Image Acquire" button is pressed, acquisition from the camera will cease, but saving to the storage medium will continue.



Button	Description
Stop Image Acquire	Stop acquiring images from the camera.
Stop Image Saving	Stop saving images to the storage medium.

7.13.1.9. Progress (Acquire, Saving)

② counts and displays the number of times the progress bar of "Acquire" reaches 100%. By checking ③, users can confirm the progress of retrieving images from the camera.


(4) counts and displays the number of times the progress bar of "Saving" reaches 100%. By checking (5), users can confirm the progress of saving images to the storage medium.

7.13.2. Saving still images.


Use the "Stop Image Acquire" button ("Stop Image Saving" button) displayed on the dialog box to control the start and stop of continuous saving of still frame images.

7.13.2.1. Start saving still images.


- 1) Open the camera to which user want to save the still image
- 2) Start the stream.
- 3) Select [View] → [Snapshot Recorder] from the menubar as shown below



4) As the result, the dialogue box shown below will open.



5) Press the "Start Image Saving" button.



- 6) Continuous image saving of still images will begin, so please wait until the image saving is complete.
- 7) When all saving is completed, the following image will be displayed, and the images will be saved to the specified folder.



(Example setting: Recording Mode: Frame Count, Frame Count: 10)

7.13.2.2. Stop saving still images.

If the user wishes to manually stop saving still images, follow the steps below:

1) Press the "Stop Image Acquire" button.

(Stop acquiring images from the camera.)



2) Press the "Stop Image Saving" button.

(Stop saving images to the storage medium.)



7.14. Tools


By selecting [Tools] from the menubar, the following features are available. These allow users to change various settings for using TeliViewer.

7.14.1.Launch "IP Configuration tool"

By selecting [Tools] → [IP Configuration Tool] from the menubar, it is possible to launch an external tool "IP Configuration tool". This allows users to change the IP address settings for any GigE camera of products of Toshiba Teli on current network.

7.14.2.**Options**

By selecting [Tools] \rightarrow [Options] from the menubar, dialog for setting the options is opened as following figure. This allows users to change various settings for TeliViewer.



7.14.2.1. Updating interval of charts

By using ① in above figure, users can change the settings for the update interval of the charts implemented in TeliViewer, such as Waveform, Vectorscope, Histogram. Default setting is 2.00 sec.

7.14.2.2. Save and restore Grid/4x4 settings

By turning ON the "Enable" checkbox ② in above figure, the state of the lines drawn in the current image can be saved/restored. Refer to the following process steps to save/restore it. Default setting is OFF.

[Steps]

- 1) Draw the "Grid" or "4x4" on current image
- 2) Turn ON the 2
- 3) When "Save now" button is pressed, TeliViewer saves the state of lines to "line configuration file". At the same time, TeliViewer saves "ModelName/SerialNumber/DeviceUserID" as the identification ID
- 4) Open the camera that was closed in above step 3). Then, if there is a "line configuration file" with an identification ID that matches the "ModelName/SerialNumber/DeviceUserID", it is read out
- 5) When streaming is started, the state of the lines that was drawn in above step 1) is restored

7.14.2.2.1. Save always when camera is closed

This feature is available when the "Enable" checkbox of ② is set to ON. If this is also set to ON, the current line drawing status is automatically saved or updated each time when camera is closed. If user want to use the data saved with the "Save now" button always and repeatedly when camera is opened, set this check box to OFF.

7.14.2.3. Save and restore camera streaming status

By turning ON the "Enable" checkbox ③ in above figure, the current streaming status of the camera can be saved/restored. Refer to the following process steps to save/restore it. Default setting is OFF.

[Steps]

- 1) Start streaming with currently opened camera
- 2) Turn ON the 3
- 3) When "Save now" button is pressed, TeliViewer saves the state of streaming to "streaming status configuration file". At the same time, TeliViewer saves "ModelName/SerialNumber/DeviceUserID" as the identification ID
- 4) Close TeliViewer
- 5) When TeliViewer is launched in next time, if there is a camera that has "ModelName/SerialNumber/DeviceUserID" matching to identification ID within "streaming status configuration file", the camera is automatically opened and the stored data in file is read out, and set to the camera
- 6) As the result, streaming status is restored

7.14.2.3.1. Save always when TeliViewer is closed

This feature is available when the "Enable" checkbox of ③ is set to ON. If this is also set to ON, the current streaming status is automatically saved or updated every time when TeliViewer is closed.

It means that if user want to restore the last working state of the TeliViewer every time when user launch it again, then set this checkbox to ON.

If user want to restore the streaming status saved with "Save now" button, and launch the TeliViewer with it every time, this checkbox should be set to OFF. By setting this to OFF, the "streaming status configuration file" will not be overwritten.

7.14.2.4. Launch with full screen

This feature is available when the "Enable" checkbox of ③ is set to ON. By setting ④ to ON, the next time TeliViewer starts up, it will launch in full screen mode.

7.14.2.5. Hide exit button and cursor on full screen

By turning ON the checkbox ⑤ in above figure, it is possible to hide the "Exit button" that appears in the bottom right corner on the full screen. Also, mouse cursor on the full screen is hidden.

In this state, to exit the full screen, press the ESC key.

7.14.2.6. Background Color


This allows users to set the background color of the image. It is available in either Black or Cobalt Blue. Default is Black.

7.14.2.7. 2in1/4in1 setting

By setting up $\widehat{\mathcal{T}}$ in above figure, the layout of the 2in1/4in1 screen can be changed. Details of each setting are as follows.

7.14.2.7.1. Display TabBar


It displays the camera identification and the current drawing information in tabbar. An example of the display is shown in the following figure. Note that this mode and "Overlay the information" cannot be selected at the same time.



69 DAA04027B

7.14.2.7.2. Overlay the information

It displays the camera identification and the current drawing information as the overlay on the image. An example of the display is shown in the following figure. Note that this mode and "Display TabBar" cannot be selected at the same time.





Attention

Regarding the impact on Overlay


This feature affects the performance of rendering. If enabled, note that the Display Rate may be slightly lower than when using the "Display TabBar".

7.14.2.7.3. Display Scrollbar

When the image extends beyond the display area, this option allows users to select whether scroll bars are displayed. When the setting is turned "ON", scroll bars will appear as shown in the following figure, and the scroll bars is available to scroll the image.

If the setting is "OFF", the scroll bar will not appear even if the image extends beyond the display area, so the display area will not be made narrower by the scroll bar. In addition, even when the scroll bar is not displayed, the image can be scrolled by using the "Scroll feature".

Users can select the most appropriate setting according to their preferences.





Attention

Regarding the scroll bars in Fit mode

Note that scroll bars are not displayed when images are displayed in Fit mode.

7.14.2.8. Enable stream stats collection

By turning ON the checkbox ® in above figure, it is possible to collect and display stream stats. This feature is available for U3V and GEV cameras. The each information for U3V/GEV can be displayed by following procedure.

1

Attention

Regarding the collection and display stream stats

Since this feature spends CPU resources, it is recommended to turn OFF when it is not required.

7.14.2.8.1. For U3V

By selecting [View] \rightarrow [Camera control] \rightarrow [U3V Info] from the menubar, users can display the "Stream stats" in U3V Info pane.

7.14.2.8.2. For GEV

By selecting [View] \rightarrow [Camera control] \rightarrow [GEV setting] from the menubar, users can display the "Stream stats" in GEV setting pane.

7.14.2.9. Enable GenTL devices

Since this feature is existing for the purpose of user support, basically use it with ON.

By turning OFF the checkbox

in above figure, GenTL devices are disabled in TeliViewer. Default setting is ON.



Attention

If it is set to OFF

Note that users cannot use the CoaXPress camera under it is OFF.

7.14.2.10. Maximum messages in Status Log

By setting the value of 1 in above figure, it is possible to change the number of messages displayed in the "<u>Status Log</u>". Default is 50.

7.14.2.11. RestoreDefault

By pressing ① in above figure, it is possible to restore the TeliViewer screen configuration, such as placement of panes or button state, to the recommended default.

7.15. Help

By selecting [Help] from the menubar, the following features are available. It will help the users according to their necessary.

7.15.1. Open user manual

By selecting [Help] \rightarrow [Open user manual] from the menubar, users can open this document "TeliViewer User manual".

7.15.2.**About**

By selecting [Help] \rightarrow [About] from the menubar, users can confirm the information related to TeliViewer, such as version number, etc.

72 DAA04027B

8. Appendix

This section describes general supplementary information for using TeliViewer.


8.1. Enlargement of the pane to the four corners

When right-clicking on the area of a pane that has no buttons, lists, or other controls, a context menu is displayed to enlarge the pane. The following four types of items are displayed. These will only be displayed when available.


- Enlarge to left
- Enlarge to right
- Enlarge to top
- Enlarge to bottom

The following is an example of "Enlarge to right" operation.

1) As following figure, "Status Log" pane does not occupy the lower right corner of the window. In this case, right-clicking on the area of a pane without any controls will display "Enlarge to right". When it is selected, the "Status Log" pane is enlarged to the right.



2) As a result, the "Status Log" pane occupies the lower right corner of the windows as following figure.



Regarding the "Enlarge to left", "Enlarge to top" or "Enlarge to bottom", almost same effect is available. It is recommended that users utilize the above procedure to obtain the most suitable placement and size of pane.

8.2. About Save/Restore settings for TeliViewer

TeliViewer automatically saves the current application state to a configuration file on the file system, when it is terminated by user operation, or when it receives the application termination signal from OS. Also, the saved state will be restored at the next launch.

The target of save/restore here is the settings for the application, such as the screen configuration of TeliViewer, or the button state of FeatureView, StatusLog, or else. Note that settings for each camera are not saved automatically. Refer to the following hints for saving/restoring settings for each camera.



To save/restore camera settings	Refer to "Save/Load camera features".
To save/restore Grid/4x4 settings	Refer to "Save and restore Grid/4x4 settings".
To restore the default state of	Refer to "RestoreDefault". If this is executed, it is possible to restore
TeliViewer	TeliViewer to the default state of the initial installation.
	[Windows]
Regarding the directory where the TeliViewer settings are saved	It will be saved to the TeliViewer.ini file under the "%APPDATA%¥TOSHIBA
	TELI¥TeliCamSDK" directory.
	[Linux based OS]
	It will be saved to the TeliViewer.ini file under the "\$HOME/.teliviewer" directory.

-	A	į.	
1	Ŧ	N	P
	•		

Attention

For Raspberry Pi OS users	Under the Raspberry Pi OS, if the OS shutdown process is executed while TeliViewer is running, the application state will not be saved. It is caused by the reason why such OS never notifies the termination signal to application at shutdown. To save the TeliViewer state under such OS, close TeliViewer by user operation, and after confirming that it is closed completely, then execute OS shutdown.
	[Note] This problem does not occur under the Windows or ubuntu OS. Even if the OS is shut down while TeliViewer is running, the state will be saved correctly.

8.3. U3V Camera Specific Information

This section describes the U3V camera specific information.

8.3.1. BERT feature

BERT (Bit Error Rate Test) is a feature that evaluates the quality of transaction between U3V camera and host. By using this feature, it is available to check the quality of signals including USB cable. Especially, when users construct the new system or update the construction of current system, it will help to check whether new system constructed by several peripherals is appropriate to work with U3V camera correctly.

The detailed technical information is opened in our web site as following:

[TECHNICAL INFORMATION: BU Series - Bit Error Rate Test]

https://www.toshiba-teli.co.jp/pdf/technology/technical/t0002 BERT.pdf

8.3.1.1. Usage of BERT feature

By following procedure, it is available to utilize BERT feature.




Attention

Regarding the OS to be used

Please use Windows OS. Under the Linux based OS, there is the case BERT cannot work correctly.

[Procedure]

- 1) By steps in "Camera Open/Close" of Discovery, open U3V camera.
- 2) By steps in "Filter Selection" in Feature View, select the "G" (Guru mode).
- 3) By using "String search" in FeatureView, input "bert" and press Enter key to search the corresponding nodes.
- 4) As the result, FeatureView will display the following figure.



- 5) By ① in above figure, select the BERTCount within the range from E9 to E12. It specifies the number of bits to be sent in a test. Please refer the technical information in the document linked above on demand.
- 6) By ② in above figure, select the BERTExecute and press the displayed "Execute" button.
- 7) When test is started, U3V camera will be closed automatically.
- 8) By steps in "Updating Camera List" of Discovery, check the recovery of U3V camera form testing.
- 9) Re-open the U3V camera with same steps in above 1).
- 10) As the result, count of Bit Error(s) is displayed within ③ in above figure. If it displays '0', it means test has finished without any error. If it displays other than '0', it means there is the possibility any peripheral that cause the transaction error is existing in current system,.



Regarding BERTCount	If larger value such as E12 is selected, it will spend much time to finish the test
	(In the case of E12, it will take 200sec around). During the test, please wait for
	finishing current test without plug out the camera.
	Under some USB controllers, in above step 8), there is the case that camera
Camera cannot recover from test after waiting much time	cannot recover and be re-discovered after waiting much time. In this case,
	please reboot the host. In most cases, by this operation, the USB controller has
	been reset, as the result, camera will recover to normal state. However, since
	BERTResult is also reset and cleared, the result of test cannot be confirmed.
	Furthermore, if you meet such situation continuously, there is the possibility that
	current USB controller potentially has problem regarding the connectivity with
	U3V camera. In such situation, it is recommended to use another USB Controller
	to narrow down the problem.

9. FAQ

Question	Answer
Tearing occurs in image	If the appropriate driver for graphics card is not installed into system, optimal performance may not be achieved. In addition, there is the case that problems such as tearing appear. For information on how to get the appropriate driver, refer to the website of the vendor of the graphics card. Note that tearing cannot be avoided on the Raspberry Pi due to graphics card performance limitations.
System freezes while streaming on Raspberry Pi	On the Raspberry Pi, there is the case that freeze phenomenon occurs while streaming from the camera. If this happens frequently, it is recommended to consider using "ubuntu MATE" instead of "Raspberry Pi OS". To use "ubuntu MATE", users need to utilize "Raspberry Pi Imager" to install the most appropriate ubuntu for the Raspberry Pi on a bootable SD card (note that this operation will erase all the data on the SD card). Next, boot ubuntu using the SD card image that was created by user, and then run "sudo apt install ubuntu-mate-desktop" from the terminal. After rebooting, the lightweight desktop "ubuntu MATE" will be available and may work as the workaround for the freezing phenomenon. [Note] For more information regarding the "Raspberry Pi Imager" and creating the OS image, refer to the Raspberry Pi OS website.
After upgrading the TeliCamSDK package, the TeliViewer screen configuration became unexpected.	Currently saved application settings may not match the new version. In that case, it is recommended to execute "RestoreDefault". After that, it will be launched with the configuration most appropriate for the current version.
Under the virtual environment, streaming of multiple cameras does not work correctly	Under such environment, even if user environment meets the hardware and software requirements, there is a possibility sufficient performance will not be achieved (It is based on the results of some our evaluation). For inquiries regarding virtual environments, such as performance issue, please contact the provider of it.
When streaming multiple cameras simultaneously, frame rate does not achieve the max performance of camera	Due to bottlenecks dependent on the OS or display adapter driver, there is the case that the display rate does not achieve sufficient performance in 2in1/4in1 mode. For streaming in 2in1/4in1 mode with high performance display rate, it is recommended to select the Linux based OS (e.g., ubuntu) on the environment that meets hardware requirements. As a result of our evaluation, there is the tendency that, on the same hardware, better performance streaming is achieved under the Linux based OS, than other OS.
Packet Lost error appears in StatusLog when streaming multiple cameras simultaneously	When the amount of data transferred from the camera exceeds the transfer capacity of the data bus on the system, there is a possibility that packet loss may occur. Even if CPU capability is sufficient, packet loss may occur if the data bus does not have sufficient bandwidth. If it is intended to stream multiple cameras at the same time, make sure that there is enough bandwidth on the data bus.

When ubuntu 22.04LTS is used with Full Wide XGA (1366 x 768) monitor, there is a case unexpected vertical line is displayed in right edge of the full screen mode

In the default window system adopted by ubuntu 22.04LTS, GNOME Desktop is selected along with Wayland. When using TeliViewer in full screen mode in this environment, there is the case that this problem will occur. Also, it has been confirmed that this problem can be solved with the workaround by selecting the Xorg or MATE Desktop for the window system. In the case when user faces this problem and has operational inconvenience, it is recommended to consider using either Xorg or MATE Desktop. The window system can be switched by selecting "Ubuntu on Xorg" or "MATE" from the session list at graphical login. In addition, it is available to select MATE Desktop by installing it with following the procedure.

"sudo apt install ubuntu-mate-desktop"

[Note]

For detailed information regarding window systems, etc., refer to the user manual of ubuntu.

10. Miscellaneous topics

10.1. Revision History

Date	Version	Description
2021/10/01	1.0.0	Initial release
2022/07/25	1.0.1	The following features are appended:
		> Histogram
		➤ Move 4x4 by mouse drag
		> Multicast
		> Save/Load XML file
		Add format for Save image as follows:
		BMP(8/24/32bpp)、PNG(8/16/24/32/48bpp)
		➤ Launch IP Configuration tool
		> Open user manual
		Also, some other modifications such as minor changes, correction of descriptions,
		etc. were applied.
2023/02/28	1.0.2	Some minor changes are applied regarding the description.
2023/05/12	1.0.3	The following features are appended:
		> StatusLog
		- Save events
		Retrieving and displaying Camera event
		Video recording
		> Options
		- Enhancement for Save and restore Grid/4x4 settings
		- Save and restore camera streaming status
		- Launch with full screen
		- Hide exit button and cursor on full screen
		- Enable stream stats collection
		- Enable GenTL devices
2024/06/20	1.0.4	The following feature is appended:
		> Image Settings
		- Image display mode: Legacy is appended
		> Snapshot Recorder
		> FeatureView
		- Save XML to file: Support GenTL device
		- Update usability of some of input operation
		> LUT Control
		- Upload/Download CSV file: Support newline code(CRLF) as separator
		Descriptions and usage for BERT
		Also, some other modifications such as minor changes, correction of descriptions,
		etc. were applied.

10.2. Disclaimer

The disclaimer for the Logging Tool follows the disclaimer for the TeliCamSDK.

The disclaimer of TeliCamSDK is described in another "License Agreement TeliCamSDK Eng.pdf".

Make sure to read this Agreement carefully before using it.

Refer to the following folder.

Windows version : [TeliCamSDK installation folder]/Licenses

Linux version : /opt/TeliCamSDK/licenses

10.3. License

TeliCamSDK consists of multiple, independent software components. Each software component is copyrighted by a third party. TeliCamSDK uses software components that are distributed as freeware under a third-party end-user license agreement or copyright notice (hereinafter referred to as a "EULA").

Some EULAs require that the source code of the applicable component be disclosed as the condition for distributing the software component in executable format. You can check the software components subject to such EULA requirements. For more information, please contact our inquiries described in section 7.4.

Toshiba Teli corporation provides a warranty for TeliCamSDK under conditions set forth by Toshiba Teli corporation. (See the following documents.

"License Agreement TeliCamSDK Eng.pdf",

"License Agreement TeliCamSDK Sample Eng.pdf")

However, some of the software components distributed under an EULA are made available for use by the user on the assumption that they are not copyrighted or warranted by a third party. These software components are licensed to the user free of charge and therefore not covered by any warranty within the scope of the applicable laws. These software components are not subject to any copyrights or other third-party rights and are provided in "as is" condition without any warranty, whether express or implied. "Warranty" here includes, but not limited to, an implied warranty for marketability

or fitness for specific uses. All risks associated with the quality or performance of these software components are assumed by the user.

EULAs are included in the following directory:

Windows version : [TeliCamSDK installation folder]/Licenses

Linux version : /opt/TeliCamSDK/licenses

Toshiba Teli corporation shall not be liable whatsoever for any cost of repair or correction or other incidental expense incurred in connection with a defect found in any of these software components. Unless specified under the applicable laws or in a written agreement, a party who changes or redistributes the software with consent from the copyright holders or based on the aforementioned licenses shall not be held liable whatsoever for any loss arising from the use of or inability to use such software components. The same applies even when the copyright holders or relevant third parties have been informed of the possibility of such loss. "Loss" here includes normal, special, incidental and indirect loss (including, but not limited to, the loss of data or its accuracy; loss incurred by the user or any third party; and interface incompatibility with other software). Please read each EULA for details on the use conditions and items that must be observed regarding these software components.

The table below lists the software components using in TeliCamSDK, which are subject to EULAs. The user should read the applicable EULAs carefully before using these software components.

Windows version

Project name	Project license
GenlCam GenApi	GenlCam License

Linux version

Project name	Project license
libteliusb (libusb)	LGPLv2.1
GenlCam GenApi	GenlCam License
Qt	LGPLv3

GenlCam GenApi uses the following third party software.

Project name	Project license
MathParser	LGPLv2.1
Log4Cpp	LGPLv2.1
CppUnit	LGPLv2.1
CLSerAll	NI license
xs3p	DSTC license
xxhash	xxhash license
XSLTProc	MIT license
XSDe	Proprietary

TeliViewer uses the following third party software.

Windows version

Project name	Project license
Qt	LGPLv3
Qwt	Qwt License
OpenGL	MIT license
GStreamer	LGPLv2

Linux version

Project name	Project license
	IJG (Independent JPEG Group) License * 1
libjpeg-turbo	Clause 2 of the Modified BSD License * 2
	zlib license
libdouble-conversion1	BSD-3-clause
Qt	LGPLv3
Qwt	Qwt License
OpenGL	MIT license
GStreamer	LGPLv2

^{* 1} This software is based in part on the work of the Independent JPEG Group.

^{* 2} Refer to "The Modified (3-clause) BSD License" in the libjpeg-turbo/LICENSE.md file in the licenses folder listed in section 10.3.

TeliCamSDK redistributes the binaries of LGPL-applied software, and for these source code only, you have the right to obtain, modify and redistribute it in accordance with the LGPL provisions.

To the customer who wants the source code, we write to the media (CD - ROM etc.) and send it by post.

Customers must pay for actual expenses such as shipping fee. If you want, please contact our inquiries described in section 7.4. We distribute source code only for open source software that you have right to obtain. (Source code of TeliCamSDK is not included.) Please understand beforehand that we cannot answer questions about the content of the source code etc.

Microsoft, Windows, Windows XP, Windows Vista, Windows 7, Windows 8.1, Windows 10, Windows 11 and Visual C++ are the trademark or the registered trademark of Microsoft Corporation.

USB3 Vision and GigE Vision are trademark or registered trademark of AIA (Automated Imaging Association) of each company.

CoaXPress is registered trademark of JIIA (Japan Industrial Imaging Association).

GenlCam is trademark of EMVA (European Machine Vision Association).

Furthermore, company name or product name might be trademark or registered trademark of each company.

10.4. Inquiry

For frequently asked questions (FAQ) and answers about TeliCamSDK, GigE cameras, USB3 cameras, and CoaXPress cameras, please visit the "Support" - "Industrial Cameras FAQ" site on <u>our website</u>.

If you still cannot solve the problem, please contact us using the phone number or Inquiries form from "Contact Us" site on <u>our website</u>.

82 DAA04027B